Brocade Flow Optimizer

REST API Guide

Supporting Flow Optimizer 1.1



© 2016, Brocade Communications Systems, Inc. All Rights Reserved.

Brocade, Brocade Assurance, the B-wing symbol, ClearLink, DCX, Fabric OS, HyperEdge, ICX, MLX, MyBrocade, OpenScript, VCS, VDX, Vplane, and Vyatta are registered trademarks, and Fabric Vision is a trademark of Brocade Communications Systems, Inc., in the United States and/or in other countries. Other brands, products, or service names mentioned may be trademarks of others.

Notice: This document is for informational purposes only and does not set forth any warranty, expressed or implied, concerning any equipment, equipment feature, or service offered or to be offered by Brocade. Brocade reserves the right to make changes to this document at any time, without notice, and assumes no responsibility for its use. This informational document describes features that may not be currently available. Contact a Brocade sales office for information on feature and product availability. Export of technical data contained in this document may require an export license from the United States government.

The authors and Brocade Communications Systems, Inc. assume no liability or responsibility to any person or entity with respect to the accuracy of this document or any loss, cost, liability, or damages arising from the information contained herein or the computer programs that accompany it.

The product described by this document may contain open source software covered by the GNU General Public License or other open source license agreements. To find out which open source software is included in Brocade products, view the licensing terms applicable to the open source software, and obtain a copy of the programming source code, please visit http://www.brocade.com/support/oscd.

Contents

Preface		7
	Document conventions	7
	Text formatting conventions	
	Command syntax conventions	
	Notes, cautions, and warnings	
	Brocade resources	
	Contacting Brocade Technical Support	
	Document feedback	
Overview of the	Flow Optimizer REST API	
	Introduction	
	Support Requirements	11
Getting Started.		13
doming ordina	Introduction	
	HTTPS Base URI	
	Authentication and Session Management	
	Authentication and Session Management Overview	
	Login	
	User Management	
	User Management Overview	
	Return List of Users	
	Create a New User	
	Edit a User	
	Delete a User	
Dashboard		27
Dasiibuaru		
	Dashboard Oversell Treffic Craph	
	Dashboard Overall Traffic Graph	
	Dashboard Overall Traffic Graph Parameters	
	Overall Traffic Graph Examples Dashboard Historical Drill Down of Overall Traffic Graph	
	Dashboard Historical Drill Down of Overall Traffic Graph Dashboard Historical Drill Down of Overall Traffic Graph	SC
	Parameters	20
	Dashboard Historical Drill Down of Overall Traffic Graph	
	Examples	30
	Dashboard Current Large Flows	
	Dashboard Current Large Flows Parameters	
	Dashboard Current Large Flows Examples	34
Flows		37
	Flows Overview	37
	Learned and Programmed Flows	
	Learned and Programmed Flows Parameters	
	Learned and Programmed Flows Examples	
	Learned Flows	41

	Learned Flows Parameters Learned Flows Examples	42
	User Defined Flows User Defined Flows Parameters	
	User Defined Flows Examples	
	Create User Defined Flow	
	Create User Defined Flow Parameters	
	Create User Defined Flow Examples	
	Delete User Defined Flow	
	Delete User Defined Flow Parameters	
	Delete User Defined Flow Examples	
Profiles		53
	Profiles Overview	
	Create New Custom Profile	
	Create New Custom Profile Parameters	
	Create New Custom Profile Examples	
	Edit Custom Profile	
	Edit Profile Parameters	
	Edit Custom Profile Examples	
	Delete Custom Profile	
	Delete Custom Profile Parameters	
	Delete Custom Profile Examples	
	Get List of ProfilesGet List of Profiles Parameters	
	Get List of Profiles Examples	
	Bulk Enabling of Profiles	
	Bulk Enabling of Profiles Parameters	
	Bulk Enabling of Profiles Examples	
	Bulk Disabling of Profiles	
	Bulk Disabling of Profiles Parameters	
	Bulk Disabling of Profiles Examples	
	Bulk Deletion of Profiles	70
	Bulk Deletion of Profiles Parameters	
	Bulk Deletion of Profiles Examples	
	Moving Profiles to the Top Priority	
	Moving Profiles to the Top Priority Parameters	
	Moving Profiles to the Top Priority Examples	
	Moving Profiles to the Bottom Priority	
	Moving Profiles to the Bottom Priority Parameters	
	Moving Profiles to the Bottom Priority Examples	15 76
	Moving Profiles Up to the Next Priority Level Parameters	
	Moving Profiles Up to the Next Priority Level Examples	
	Moving Profiles Down to a Lower Priority Level	
	Moving Profiles Down to a Lower Priority Level Parameters	
	Moving Profiles Down to a Lower Priority Level Examples	
Settings		01
ocungs	Settings Overview	
	Controller Settings	
	Controller Settings Parameters	
	Controller Settings Farameters	
	Add Controller Settings	
	Add Controller Settings Parameters	84
	Add Controller Settings Examples	

Edit Controller Settings	85
	s86
Edit Controller Settings Examples	86
Email Notification Settings	87
Email Test Settings	88
Email Notification Settings Parame	ters88
Email Notification Settings Example	es89
Add Email Settings	91
Add Email Settings Parameters	91
	91
Update Email Settings	
	93
	93
Retrieve sFlow Settings, SNMP and sFlow	
Retrieve sFlow Settings, SNMP and	
	95
	d sFlow Registration Examples95
Add sFlow Settings	
	97
	97
Update Existing sFlow Settings	
	rameters99
	amples99
Retrieve SNMP Profiles	
	101
	101
Create SNMP Profile	
	103
	104
Update Existing SNMP Profile	
	ameters105
	mples105
Delete Existing SNMP Profile	
	meters107
Delete Existing SniviP Profile Exam	nples107
Device Management	
Device Management	
Retrieve Controller and Managed Devices.	
	Devices Parameters110
	Devices Examples110
Register Devices	
	112
	113
Update Registered Managed Devices	
	es Parameters115
	es Examples116
De-register Managed Devices	
	meters118
De-register Managed Devices Exar	nples119
Events	121
Events Overview	
Retrieve Events	
	122
Retrieve Events Examples	122

Protocol Suppo	t	125
. пососон о шрро	Protocol Support Default HTTPS	
ContentType Su	pport	127
	ContentType Support REST Requests	
	Accept HTTPS Request Header	
	Content-type HTTPS Request Header	128
Error Handling		129
J	Error Handling	
	URI Return Behavior	136

Preface

Document conventions	7
Brocade resources	9
Contacting Brocade Technical Support	9
Document feedback	

Document conventions

The document conventions describe text formatting conventions, command syntax conventions, and important notice formats used in Brocade technical documentation.

Text formatting conventions

Text formatting conventions such as boldface, italic, or Courier font may be used in the flow of the text to highlight specific words or phrases.

Format	Description
bold text	Identifies command names
	Identifies keywords and operands
	Identifies the names of user-manipulated GUI elements
	Identifies text to enter at the GUI
italic text	Identifies emphasis
	Identifies variables
	Identifies document titles
Courier font	Identifies CLI output
	Identifies command syntax examples

Command syntax conventions

Bold and italic text identify command syntax components. Delimiters and operators define groupings of parameters and their logical relationships.

Convention	Description
bold text	Identifies command names, keywords, and command options.
italic text	Identifies a variable.
value	In Fibre Channel products, a fixed value provided as input to a command option is printed in plain text, for example,show WWN.

Convention	Description
[]	Syntax components displayed within square brackets are optional.
	Default responses to system prompts are enclosed in square brackets.
{ x y z }	A choice of required parameters is enclosed in curly brackets separated by vertical bars. You must select one of the options.
	In Fibre Channel products, square brackets may be used instead for this purpose.
x y	A vertical bar separates mutually exclusive elements.
<>	Nonprinting characters, for example, passwords, are enclosed in angle brackets.
	Repeat the previous element, for example, <i>member[member</i>].
\	Indicates a "soft" line break in command examples. If a backslash separates two lines of a command input, enter the entire command at the prompt without the backslash.

Notes, cautions, and warnings

Notes, cautions, and warning statements may be used in this document. They are listed in the order of increasing severity of potential hazards.

NOTE

A Note provides a tip, guidance, or advice, emphasizes important information, or provides a reference to related information.

ATTENTION

An Attention statement indicates a stronger note, for example, to alert you when traffic might be interrupted or the device might reboot.



CAUTION

A Caution statement alerts you to situations that can be potentially hazardous to you or cause damage to hardware, firmware, software, or data.



DANGER

A Danger statement indicates conditions or situations that can be potentially lethal or extremely hazardous to you. Safety labels are also attached directly to products to warn of these conditions or situations.

Brocade resources

Visit the Brocade website to locate related documentation for your product and additional Brocade resources.

You can download additional publications supporting your product at www.brocade.com. Select the Brocade Products tab to locate your product, then click the Brocade product name or image to open the individual product page. The user manuals are available in the resources module at the bottom of the page under the Documentation category.

To get up-to-the-minute information on Brocade products and resources, go to MyBrocade. You can register at no cost to obtain a user ID and password.

Release notes are available on MyBrocade under Product Downloads.

White papers, online demonstrations, and data sheets are available through the Brocade website.

Contacting Brocade Technical Support

As a Brocade customer, you can contact Brocade Technical Support 24x7 online, by telephone, or by e-mail. Brocade OEM customers contact their OEM/Solutions provider.

Brocade customers

For product support information and the latest information on contacting the Technical Assistance Center, go to http://www.brocade.com/services-support/index.html.

If you have purchased Brocade product support directly from Brocade, use one of the following methods to contact the Brocade Technical Assistance Center 24x7.

Online	Telephone	E-mail
Preferred method of contact for non-urgent issues:	Required for Sev 1-Critical and Sev 2-High issues:	support@brocade.com Please include:
 My Cases through MyBrocade Software downloads and licensing tools Knowledge Base 	 Continental US: 1-800-752-8061 Europe, Middle East, Africa, and Asia Pacific: +800-AT FIBREE (+800 28 34 27 33) For areas unable to access toll free number: +1-408-333-6061 Toll-free numbers are available in many countries. 	Problem summarySerial numberInstallation detailsEnvironment description

Brocade OEM customers

If you have purchased Brocade product support from a Brocade OEM/Solution Provider, contact your OEM/Solution Provider for all of your product support needs.

- OEM/Solution Providers are trained and certified by Brocade to support Brocade® products.
- Brocade provides backline support for issues that cannot be resolved by the OEM/Solution Provider.

- Brocade Supplemental Support augments your existing OEM support contract, providing direct access to Brocade expertise. For more information, contact Brocade or your OEM.
- · For questions regarding service levels and response times, contact your OEM/Solution Provider.

Document feedback

To send feedback and report errors in the documentation you can use the feedback form posted with the document or you can e-mail the documentation team.

Quality is our first concern at Brocade and we have made every effort to ensure the accuracy and completeness of this document. However, if you find an error or an omission, or you think that a topic needs further development, we want to hear from you. You can provide feedback in two ways:

- Through the online feedback form in the HTML documents posted on www.brocade.com.
- By sending your feedback to documentation@brocade.com.

Provide the publication title, part number, and as much detail as possible, including the topic heading and page number if applicable, as well as your suggestions for improvement.

Overview of the Flow Optimizer REST API

•	Introduction	1	1
•	Support Requirements	. 1	1

Introduction

This document details the REST API, a programmatic interface, that is supported in this Brocade Flow Optimizer (BFO) for Release 1.1. This interface is built for third party consumption as well as BFO clients.

The Brocade Flow Optimizer REST API exposes services perform CRUD operation for profiles, and other higher level services, including but not limited to retrieval of the following data:

- · Performance data
- Events

This document covers details on the Brocade REST API interface, including basic to higher level functionality within the scope of this release.

Support Requirements

This topic covers a list of support requirements for the Brocade Flow Optimizer (BFO) REST API.

BFO support requirements include but are not limited to the following:

- · Support REST interface for getting the list of Profiles.
- · Support REST interface for getting different settings in BFO.
- Support REST interface for getting Historical and Real Time performance data.
- Support REST interface for getting list of Traffic Flows from BFO with filter option.
- · Support REST interface for getting list of EVENTS from BFO with filter options.
- Support REST interface for Create / Edit / Delete / Enable / Disable / Change Priority of the Custom Profiles.
- · Support REST interface for Create / Delete user defined Custom Flow.
- · Support REST interface for Add / Edit / Delete different settings in BFO.
- Support both XML and JSON payloads based on user input for all REST based requests.
- · Support for both XML and JSON content types.
- Support authentication of every web service request.

Support Requirements

Getting Started


•	Introduction	13
•	Authentication and Session Management	.14
•	User Management	.17

Introduction

This chapter describes how to get started using the Brocade Flow Optimizer (BFO) REST API.

This Brocade Flow Optimizer (BFO) REST API guide provides details of the REST programmatic interface that is supported in the BFO release 1.1. The BFO REST API interface is built for third party consumption as well as BFO clients in-house.

The BFO REST API aims at exposing services to perform create, retrieve, update, and delete (CRUD) operations for profiles, and in addition other higher level services such as getting performance data, events, and settings. This document attempts to state in detail how we will provide the REST interface for basic and higher level functionality.



The following information to get started using the BFO is provided in this chapter as follows:

- · Base URI where all REST operations are performed.
- · Authentication and session management.

HTTPS Base URI

The Brocade Flow Optimizer (BFO) base URI protocol support is exclusively supported for HTTPS, and not for HTTP, and REST HTTPS requests are not accepted.

All REST operations will be provided at the following base context path.

TABLE 1 HTTPS Protocol Support

HTTPS Default Port	HTTPS URL
8089	https:// <bfo ip="" server="">:8089</bfo>

Authentication and Session Management

Authentication and Session Management Overview

Only a valid Brocade Flow Optimizer (BFO) user can use web services for authentication and session management, requiring a login (consisting of a valid non-empty password.)

The REST interface provides two operations:

- · Login of a client session.
- · Logout of a client session.

Login

This topic covers steps for logging in to the Brocade Flow Optimizer (BFO) server.

Resource URL

<Base URI>/collector/login

All REST operations will be provided at the following base context path in the URI field of your REST client tool.

To login to the BFO server, complete the following steps.

- 1. Login to the BFO server by entering the following URI in the URL field of your REST client tool: https://localhost:8089/collector/login
- 2. Define the login parameters.
- 3. Set the HTTPS request method to POST.

Login Parameters

This topic covers login parameters for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Username	The valid BFO user name.
Password	Valid clear text password.

NOTE

The POST operation is supported.

Login Examples

This topic covers login examples for the Brocade Flow Optimizer (BFO) server.

Login examples for BFO POST operation for login include:

- BFO URI
- · BFO Login request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/login

Example of Login Request Headers Sent to BFO

The following is an example of login request headers sent. ${\tt JSON}$

Request header

```
{
Accept - Application/json
Content-Type - Application/json
Request payload
}

Request body
{
"username": "Administrator",
"password": "pass"
}

Response body
```

"token": "Administrator_1426620456948",
"status": "Login success"

XML:

Request header

```
Accept - Application/xml
Content-Type - Application/xml
```

Request payload

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<login>
<username>Administrator</username>
<password>pass</password>
</login>
```

Response body

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<login>
<token>Administrator_1426270596791</token>
<status>Login success</status>
</login>
```

TABLE 2 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
401 Unauthorized	FAILED, reason included in HTTPS error response

If the login request is successful, BFO will send the authorized token, which will be used for the other REST operations.

NOTE

Login object contains the token that can be used for authorization of other REST requests.

User Management

User Management Overview

User Management URIs allow users to return a list of users, create a new user, edit a user, and delete a user in the Brocade Flow Optimizer (BFO).

The REST interface provides these operations:

- · Returning a list of users.
- · Creating new users.
- Editing new users.
- · Deleting new users.

Return List of Users

Return the list of users created in the Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/users

All REST operations will be provided at the following base context path in the URI field of your REST client tool.

To return the list of users created in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ users
- 2. Define the return list of users parameters.
- 3. Set the HTTPS request method to GET.

Return List of Users Parameters

This topic covers retrieving the list of users parameters for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	GET

NOTE

The GET operation is supported.

Return List of Users Examples

Get list of users examples for BFO GET operation include:

- BFO URI
- · BFO get users request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://<BFO Server IP>:8089/collector/users

Example of Login Request Headers Sent to BFO

The following is an example of return list of users headers sent. ${\tt JSON}$

Request header

```
Authorization - Administrator_1426270596791
Accept - Application/json
}

Response body
{
  "user": [
    {
        "name": "Administrator",
        "access_privilege": -1,
        "created_on": "Tue Dec 23 09:24:50 PST 2014",
        "last_modified_on": "Tue Dec 23 09:24:50 PST 2014"
},
    {
        "name": "Guest",
        "access_privilege": 0,
        "created_on": "Fri Mar 13 10:31:33 PDT 2015",
        "last_modified_on": "Fri Mar 13 10:31:33 PDT 2015",
        "last_modified_on": "Fri Mar 13 10:31:33 PDT 2015"
}
```

XML

Request header

Authorization - Administrator_1426270596791 Accept - Application/xml

Response body

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<users>
<user>
<name>Administrator</name>
<access_privilege>-1</access_privilege>
<created_on>Tue Dec 23 09:24:50 PST 2014</created_on>
<last_modified_on>Tue Dec 23 09:24:50 PST 2014</last_modified_on>
</user>
<user>
<name>Guest</name>
<access_privilege>0</access_privilege>
<created_on>Fir Mar 13 10:31:33 PDT 2015</created_on>
<last_modified_on>Fri Mar 13 10:31:33 PDT 2015</last_modified_on>
</user>
</user>
</user>
</user>
</user>
</user>
</user>
</user>
```

TABLE 4 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS, on successful code the list of users are returned
401 Unauthorized	FAILED, reason included in HTTPS error response

Create a New User

This topic covers the process of creating a new user in Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/users/<user name>

Before creating a new user in the BFO, criteria for creating a user are as follows:

- Only a user with Admin privileges (access_privilege=1) is allowed to create a new user.
- · Valid username name and password are required as input.
- Access privilege is optional, and if not provided, created user will have operational privileges (access privilege=0).
- · A user cannot be created with same name as another user.

NOTE

BFO is limited to one default administrator. The default administrator is the only BFO user with administrative privileges. The default administrator cannot assign administrative privileges to other users.

To create a new user in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ users/<user name>
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to POST.

Creating New User Parameters

This topic covers parameters for creating a new user for the Brocade Flow Optimizer (BFO).

Authorized token.
The content type of the returned data.
JSON format: Application/json
XML format: Application/xml
POST
-

NOTE

The POST operation is supported.

Creating New User Examples

This topic covers creating a new user examples for the Brocade Flow Optimizer (BFO) server.

Creating a new user examples for BFO POST operation for login include:

- · BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

```
https://<BFO Server IP>:8089/collector/users
```

Example of Headers Sent to BFO

The following is an example of creating a new user request headers sent. ${\tt JSON}$

```
Request header
```

```
{
Accept - Application/json
Content-Type - Application/json
}

Request body
{
"name": "GuestTwo",
"password": "guest_two"
"access_privilege": 1
```

XML

Request header

Request payload

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<user>
<name>GuestTwo</name>
<password>guest_two</password>
<access_privilege>0</access_privilege>
</user>
```

TABLE 5 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS, on successful code the list of users are returned
401 Unauthorized	FAILED, reason included in HTTPS error response

On successful completion, new user will created in the BFO.

Edit a User

Updating a single user in the Brocade Flow Optimizer (BFO). Only a user with Admin privileges (access_privilege=1) is allowed to update an existing user. Password and access_privilege can be updated. User by the name Administrator is root user and cannot be updated.

Resource URL

<Base URI>/collector/users/<user name>

Before editing a user in the BFO, criteria for editing a user are as follows:

- Only a user with Admin privileges (access privilege=1) is allowed to edit a user.
- · Valid username name and password are optional as input.
- · A user by the name Administrator is a root user and cannot be updated.

All REST operations will be provided at the following base context path in the URI field of your REST client tool.

To edit the existing user in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ users/<user name>
- 2. Define the updated user parameters.
- 3. Set the HTTPS request method to PUT.

Editing User Parameters

This topic covers parameters for editing a user for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	PUT

NOTE

The PUT operation is supported.

Editing User Examples

This topic covers editing a user examples for the Brocade Flow Optimizer (BFO) server.

Editing a user examples for BFO PUT operation for login include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/users/<username>

Example of Headers Sent to BFO

The following is an example of edit user request headers sent. JSON

Request header

```
Authorization - Administrator_1426270596791
Accept - Application/json

Request payload:
{
    "password": "guest_two_updated",
    "access_privilege": 0
}
```

XML

Request header

```
Authorization - Administrator_1426270596791
Accept - Application/xml
```

Request payload

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<user>
<password>guest_two_updated</password>
<access_privilege>0</access_privilege>
</user>
```

TABLE 6 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS, on successful code the list of users are returned
401 Unauthorized	FAILED, reason included in HTTPS error response

On successful completion, new user will edited in the BFO.

Delete a User

This topic covers the process of deleting a single user. Only a user with Admin privileges (access_privilege=1) is allowed to delete an existing user.

Resource URL

```
<Base URI>/collector/users/<user name>
```

All REST operations will be provided at the following base context path in the URI field of your REST client tool.

To delete the existing user in the BFO, complete the following steps.

NOTE

User by the name Administrator is the root user and cannot be deleted.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ users/<username>
- 2. Define the deleted user parameters.
- 3. Set the HTTPS request method to DELETE.

Deleting User Parameters

This topic covers parameters for deleting a user for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	DELETE

NOTE

The DELETE operation is supported.

Deleting User Examples

This topic covers deleting user examples for the Brocade Flow Optimizer (BFO) server.

Deleting a user examples for BFO PUT operation for login include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/users/<username>

Example of Headers Sent to BFO

The following is an example of the delete user request headers sent. $\ensuremath{\mathtt{JSON}}$

Request header

Authorization - Administrator_1426270596791 Content-Type - Application/json

XML

Request header

Authorization - Guest 1426270596791 Accept - Application/ $\overline{x}ml$

TABLE 7 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS, on successful code the list of users are returned
401 Unauthorized	FAILED, reason included in HTTPS error response

On successful completion, user will edited in the BFO.

Deleting User Examples

Dashboard

Dashboard Overview	27
Dashboard Overall Traffic Graph	27
Dashboard Historical Drill Down of Overall Traffic Graph	30
Dashboard Current Large Flows	33

Dashboard Overview

Dashboard is a monitoring section of the Brocade Flow Optimizer (BFO). The Dashboard REST API URI's retrieve the list of Large Flows that BFO has identified, based on user configured profiles.

Dashboard REST URI's provide some of the vital statistics listed below.

- · Total traffic BFO is processing or receiving.
- · Total traffic (Mbps) dropped.
- Total traffic (Mbps) passed. This include the traffic BFO has not marked as large flow.
- · List of Large Flows identified by Default and Custom Profiles.

Dashboard Overall Traffic Graph

This topic covers the process of accessing the overall traffic graph. This API returns the Overall traffic utilization (Dropped + Passed) for the last 1 minute. Each API call returns the last 1 minute of data (Passed Traffic and Dropped Traffic).

Resource URL

<Base URI>/collector/utilization/overallTraffic

All REST operations will be provided at the following base context path in the URI field of your REST client tool.

To access the overall traffic graph in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ utilization/overallTraffic
- 2. Define the overall traffic user parameters.
- 3. Set the HTTPS request method to GET.

Dashboard Overall Traffic Graph Parameters

This topic covers parameters for the overall traffic graph for the Brocade Flow Optimizer (BFO).

Authorized token.
The content type of the returned data.
JSON format: Application/json
XML format: Application/xml
GET

NOTE

The GET operation is supported.

Overall Traffic Graph Examples

This topic covers overall traffic graph examples for the Brocade Flow Optimizer (BFO) server.

Overall traffic graph examples for BFO GET operation for overall traffic include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/utilization/overallTraffic

Example of Headers Sent to BFO

The following is an example of overall traffic graph request headers sent. ${\tt JSON}$

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json
```

Response Body

XML

Request header

Authorization - Administrator 1426270596791 Content-Type - Application/xm \overline{l}

TABLE 8 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

The utilization data of Blocked Traffic and Passed Traffic will be returned in the response. The data will cover the last 30 minutes, with 1 minute granularity on initial load. Every 1 minute, the utilization for the current minute will be updated.

Dashboard Historical Drill Down of Overall Traffic Graph

This topic covers the process of returning the historical data of the overall traffic graph. The Brocade Flow Optimizer (BFO) supports historical data retained for the past 30 minutes, 1 hour, 1 day, 1 week, or 30 days.

Resource URL

<Base URI>/collector/utilization/detailOverallTraffic

The dashboard historical drill down of overall traffic graph API returns the top 5 large flows (by BW utilized) for the time range selected. The user can retrieve the flows for dropped and passed traffic.

All REST operations will be provided at the following base context path in the URI field of your REST client tool.

To retrieve the historical overall traffic data in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ utilization/detailOverallTraffic
- 2. Define the return list of parameters.
- 3. Set the HTTPS request method to POST.

Dashboard Historical Drill Down of Overall Traffic Graph Parameters

This topic covers parameters for the historical drill down of overall traffic graph for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	POST

NOTE

The POST operation is supported.

Dashboard Historical Drill Down of Overall Traffic Graph Examples

This topic covers historical drill down of overall traffic graph examples for the Brocade Flow Optimizer (BFO) server.

Historical drill down of overall traffic graph examples for BFO POST operation for overall traffic include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://<BFO Server IP>:8089/collector/utilization/detailOverallTraffic

Example of Headers Sent to BFO

The following is an example of dashboard historical drill down of overall traffic graph request headers sent.

JSON

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json
Request Body
   "startTime": 0,
   "endTime": 0,
"duration": 1800000,
"mitigationType": "NONE"
Response Body
   "startTime":1440161280000,
"endTime":1440163079000,
"granularity_ms":60000,
"mitigationType":"NONE",
"topFlows":[
           "id":296657552,
"rank":1,
           "percentage":100,
"totalUtil": 542,
"utilization":[
               1371,
               1379,
               1395,
               1368,
               1363,
               1343,
               1395,
               1368,
               1373,
               1347,
               1382,
               1370,
               1359,
               1387,
               1368,
               1375,
1372,
               1376,
               1364,
               1376,
               1351,
               1395,
               1382,
               1370,
               1373,
               1386,
               1368,
               1375,
               1354,
               0
          1,
"srcIp":"10.10.10.4",
"destIp":"30.30.30.4",
"srcMac":"00:24:38:7c:7e:00",
"destMac":"00:24:38:ae:cb:00",
"srcPort":53,
           "destPort":60,
"inVlan":20
    ],
"otherFlows":[
```

```
}
```

XML

Request header

```
Authorization - Administrator 1426270596791 Content-Type - Application/xm\overline{l}
```

Request Body

TABLE 9 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

The utilization data for the specified duration will be retrieved in the response.

Dashboard Current Large Flows

This topic covers the process of returning the list of Large flows identified for default profiles and custom profiles in the Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/utilization/profileTraffic

The dashboard current large flows will return the list of the flows sorted by BW utilization.

All REST operations will be provided at the following base context path in the URI field of your REST client tool.

To retrieve the list of the flows sorted by BW utilization in the BFO, complete the following steps.

- 1. Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/utilization/profileTraffic
- 2. Define the return list of parameters.
- 3. Set the HTTPS request method to GET.

Dashboard Current Large Flows Parameters

This topic covers parameters for the current large flows for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	GET

NOTE

The GET operation is supported.

Dashboard Current Large Flows Examples

This topic covers current large flows examples for the Brocade Flow Optimizer (BFO) server.

Current large flows examples for BFO GET operation for overall traffic include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/utilization/profileTraffic

Example of Headers Sent to BFO

The following is an example of dashboard current large flows request headers sent. ${\tt JSON}$

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json
             Response Body
                "profileUtilization":[
                       "id":1,
"name":"NTP_Reflection",
                       "type":0,
"action":"NONE",
                       "threshold":null,
"utilization":null,
"attacks":null
                       "id": 1,
"name": "NTP_Reflection",
"type": 0,
"action": "NONE",
"threshold": null,
"utilization": null,
"attacks": [
                                 "attackId": "Destination:219.219.219.120-L3_PROTOCOL:UDP-
"utilization": 142,
"trafficPercentage": 0,
                                 "network attributes": [
                                    "name": "Destination",
"value": "219.219.219.120"
                             }
                        ]
                       "id":2,
"name":"DNS_Reflection",
                       "type":0,
"action":"NONE",
"threshold":null,
                        "utilization":null,
"attacks":null
                       "id":4,
"name":"ICMP_Flood",
"type":0,
"action":"NONE",
"threshold":null,
"utilization":null,
"attacks":null
                       "id":5,
"name":"CharGen",
"type":0,
"action":"NONE",
"threshold":null,
"this attion":nul
                        "utilization":null,
"attacks":null
                    },
                       "id":6,
"name":"Quote_Of_The_Day",
"type":0,
```

```
"action":"NONE",
"threshold":null,
"utilization":null,
"attacks":null
},

{
   "id":7,
   "name":"Simple_Service_Discovery_Protocol",
   "type":0,
   "action":"NONE",
   "threshold":null,
   "utilization":null,
   "attacks":null
},

{
   "id":3,
   "name":"UDP_Flood",
   "type":0,
   "action":"NONE",
   "threshold":null,
   "utilization":null,
   "utilization":null,
   "attacks":null
},

{
   "id":101,
   "name":"Custom Profile",
   "type":1,
   "action":"METER",
   "threshold":null,
   "utilization":null,
   "utilization":null,
   "attacks":null
}
}
```

TABLE 10 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

Flows

Flows Overview	37
Learned and Programmed Flows	37
Learned Flows	
User Defined Flows	45
Create User Defined Flow	49
Delete User Defined Flow	51

Flows Overview

Flows is a URI to fetch learned and programmed flows with Utilization as Mbps.

Flows REST URI provides some of the features listed below.

- · Learned flows with utilization as Mbps.
- · Programmed flows with utilization as Mbps.

Learned and Programmed Flows

This topic covers the process of learned and programmed flows. This API returns learned and programmed flows with utilization as Mbps. Only the active flows for last 15 seconds are returned in the response.

Resource URL

<Base URI>/collector/flows/largeFlows

All REST operations will be provided at the following base context path in the URI field of your REST client tool.

To access learned and programmed flows in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ flows/largeFlows
- 2. Define the overall traffic user parameters.
- 3. Set the HTTPS request method to POST.

Learned and Programmed Flows Parameters

This topic covers parameters for learned and programmed flows for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	POST

NOTE

The POST operation is supported.

Learned and Programmed Flows Examples

This topic covers learned and programmed flows fetch request for the Brocade Flow Optimizer (BFO) server.

Learned and programmed flows fetch request examples for BFO POST operation for flows include:

- BEO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/flows/largeFlows

The following is an example of learned and programmed flows fetch request headers sent.

Request header Authorization - Administrator_1426270596791 Content-Type - Application/json Request Body "page_size": "1", "page_range": "1-2", "filters": { "network_attribute": ["name": "SRC MAC", "value": "00:24:38:80:8e:00-V4" "name": "V4_DEST_ADDR", "value": "10.1.1.4" "name": "IN_VLAN", "value": "10"], "profile name": "Custom Profile", // to filter by profile name "profile_type": "0", // to filter by profile type 0- Default, 1-Custom Profile "action": "None" // to filter by action Response Body "page_size": 1, "total_pages": 250, "timestamp": 1440505824364, "page": ["number": 1, "large_flow": [{ "id": "FlowKey_1", "utilization": 25000, "identifiedOn": 1440505824, "profileId": 1, "profileName": "Custom Profile_0", "profileType": 1, "profileAction": "None", "12 network_attributes": ["name": "SRC MAC", "value": "00:24:38:80:8e:00-V4", "label": "Source Mac" }, "name": "DEST_MAC", "value": "00:0a:95:9d:68:16-V4", "label": "Destination Mac"], "13_network_attributes": ["name": "V4 DEST ADDR", "value": "10.10.1.1", "label": "Destination IP"], "14_network_attributes": [

"name": "UDP SRC PORT",

```
"value": "123",
"label": "UDP Source Port"
                                         }
                               ]
                        }
                 ]
           },
                       "number": 2,
"large_flow": [
                                      "id": "FlowKey_2",
"utilization": 12500,
"identifiedOn": 1440505824,
                                      "laentifledon": 1440505824,
"profileId": 2,
"profileName": "Custom Profile_1",
"profileType": 1,
"profileAction": "None",
"12 network_attributes": [
                                                      "name": "SRC_MAC",
"value": "00:24:38:80:8e:00-V4",
"label": "Source Mac"
                                          },
{
                                                      "name": "DEST_MAC",
"value": "00:0a:95:9d:68:16-V4",
"label": "Destination Mac"
                                  ], "13_network_attributes": [
                                                      "name": "V4 DEST ADDR",
"value": "10.10.1.1",
"label": "Destination IP"
                                      "l4_network_attributes": [
                                                      "name": "UDP_SRC_PORT",
"value": "123",
"label": "UDP Source Port"
                                  ]
                         }
                 ]
          }
   "filters": {
               "network attribute": [
                  {
                              "name": "SRC_MAC",
"value": "00:24:38:80:8e:00-V4"
                   },
                              "name": "V4_DEST_ADDR",
"value": "10.1.1.4"
                   },
                              "name": "IN_VLAN", "value": "10"
               "profile_name": "Custom Profile", "action": "None"
}
```

TABLE 11 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS

TABLE 11 Status Code (Continued)

400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

Learned Flows

This topic covers how to retrieve a list of all active flows. By default, the details (utilization in Mbps) will be fetched for the last 30 minutes.. The Filter criteria can be set based on learned flows entries.

Resource URL

<Base URI>/collector/flows/allFlows

The learned flows REST URI provides some of the features listed below.

- · Bandwidth utilization.
- · Network attributes.

All REST operations will be provided at the following base context path in the URI field of your REST client tool.

To access learned and programmed flows in the BFO, complete the following steps.

- 1. Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/flows/allFlows
- 2. Define the overall traffic user parameters.
- 3. Set the HTTPS request method to POST.

Learned Flows Parameters

This topic covers parameters for learned flows for the Brocade Flow Optimizer (BFO).

Parameter Value
Authorized token.
The content type of the returned data. JSON format: Application/json XML format: Application/xml
POST

NOTE

The POST operation is supported.

Learned Flows Examples

This topic covers learned flows fetch request for the Brocade Flow Optimizer (BFO) server.

Learned flows fetch request examples for BFO POST operation for flows include:

- BFO URI
- · BFO request headers sent

Request data criteria includes the following.

- Pagination Support is available. The response data is populated based on page size and page range.
- · Filters the data based on network attribute. See the Example of BFO URI.
- Filtering based on Bandwidth utilization. A value of zero is optional as it will be excluded.
 - Equals 500 Mbps:

```
"minUtil" : 500, 
"maxUtil" : 500
```

· Greater than 300 Mbps:

```
"minUtil" : 300 ,
"maxUtil" : "0"
```

· Greater than 250 Mbps:

```
"minUtil" : 0 ,
"maxUtil" : 250
```

· Retrieve all values or based on filter criteria.

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/flows/allFlows

The following is an example of learned flows fetch request headers sent. JSON

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json
Request Body
            "page size": 20,
"total pages": 51,
"timestamp": 1445418054068,
             "page": [
                                      "number": 1,
"traffic_flow": [
                                                  {
                                                               "id": 109035286,
"utilization": 539.57,
"source_mac": "00:00:82:8a:e5:83",
"destination_mac": "00:24:38:93:f7:00",
"in_vlan": 218,
"in_priority": 0,
                                                               "in priority": 0,

"ip_tos": 0,

"source_ip": "218.218.218.115",

"destination ip": "219.219.219.115",

"ip_protocol": "UDP",

"source_port": 123,

"destination_port": 63,

"action": "NONE"
                                                                "action": "N\overline{O}NE",
                                                                "vni": null,
                                                               "vni": null,

"inner source_mac": "",

"inner_destination_mac": "",

"inner_ip_fragment": 0,

"inner_source_ip": "",

"inner_destination_ip": "",

"inner_ip_protocol": "",

"inner_is_ipv6 flow": false,

"ip_type": "IPV_4"
                                                   },
                                                 {
                                                   . . .
                                                    . . .
                                                } ,
                                                                "id": 3977559602,
                                                                "utilization": 267.77,
"source mac": "00:00:7d:ea:5a:b1",
"destination_mac": "00:24:38:93:f7:00",
"in_vlan": 2I2,
                                                                "in_priority": 0,
                                                               "in_priority": 0,
"ip_tos": 0,
"source_ip": "212.212.212.57",
"destination_ip": "213.213.213.57",
"ip_protocol": "UDP",
"source_port": 63,
"destination_port": 63,
"action": "NONE",
"vni": null,
"inner_source_mac": ""
                                                                "inner_source_mac": "",
"inner_destination_mac": "",
                                                               "inner_destination_mac": "",
"inner_ip_fragment": 0,
"inner_source_ip": "",
"inner_destination_ip": "",
"inner_ip_protocol": "",
"inner_is_ipv6_flow": false,
"ip_type": "IPV_4"
                                                   }
                                     ]
             "filters": null
```

```
}
Response
The Traffic Flow details along with utilization will be sent in
the response.
Response Body
        "page size": 1,
"total_pages": 250,
"timestamp": 1440505824364,
         "page": [
                         "number": 1,
                         "large_flow": [
                                          "id": "FlowKey_1",
"utilization": 25000,
"identifiedOn": 1440505824,
                                          "identifiedOn": 1440505824,

"profileId": 1,

"profileName": "Custom Profile_0",

"profileType": 1,

"profileAction": "None",

"12_network_attributes": [

{
                                                          "name": "SRC_MAC",
"value": "00:24:38:80:8e:00-V4",
"label": "Source Mac"
                                              },
                                                          "name": "DEST_MAC",
"value": "00:0a:95:9d:68:16-V4",
"label": "Destination Mac"
                                     ],
"13_network_attributes": [
                                                           "name": "V4_DEST_ADDR",
"value": "10.10.1.1",
"label": "Destination IP"
                                      ], "14_network_attributes": [
                                                          "name": "UDP SRC_PORT",
"value": "123",
"label": "UDP Source Port"
                                     ]
                           }
                   ]
            },
{
                         "number": 2,
"large_flow": [
                             {
                                          "id": "FlowKey_2",
"utilization": 12500,
"identifiedOn": 1440505824,
                                         "ldentifiedOn": 1440505824,

"profileId": 2,

"profileName": "Custom Profile_1",

"profileType": 1,

"profileAction": "None",

"12_network_attributes": [
                                                           "name": "SRC_MAC",
"value": "00:24:38:80:8e:00-V4",
"label": "Source Mac"
                                                          "name": "DEST_MAC",
"value": "00:0a:95:9d:68:16-V4",
"label": "Destination Mac"
                                      ],
"13_network_attributes": [
```

TABLE 12 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

User Defined Flows

This topic covers the process of user defined flows, which is a POST operation for creating a CustomFlows search, returning a list of CustomFlows.

Resource URL

<Base URI>/collector/customflows/search?
startpage=<value>&noofpages=<value>&pagesize=<value>

The CustomFlows object is a paginated resource containing a list of CustomFlow instances. Each CustomFlows object represents a page of the resource. The API provides the user with three query parameters startpage, noofpages, and pagesize.

- The startpage parameter indicates the starting number of the first page of data.
- The noofpages parameter indicates the number of pages to be returned which equates to the number of CustomFlows object instances.
- The pagesize parameter indicates the number of elements per page, which equates to the number of CustomFlow instances within the CustomFlows object instance.

If the startpage query parameter is null, then all CustomFlows object instances are returned. It startpage is not null and > 0 but noofpages and pagesize are null, then number of pages and pagesize are defaulted to 5 and 50 respectively.

All REST operations will be provided at the following base context path in the URI field of your REST client tool.

To access learned and programmed flows in the BFO, complete the following steps.

- 1. Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/customflows/search?startpage=<value>&noofpages=<value>&pagesize=<value>
- 2. Define the overall traffic user parameters.
- 3. Set the HTTPS request method to GET.

User Defined Flows Parameters

This topic covers parameters for user defined flows for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	POST
Query Parameter	Parameter Value
startpage	Start page.
noofpages	Number of pages to be returned.
pagesize	Number of records per page.
NOTE	
The POST operation is supported.	

User Defined Flows Examples

This topic covers the fetch request for user defined flows for the Brocade Flow Optimizer (BFO) server.

User defined flows fetch request examples for BFO POST operation for flows include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/flows/largeFlows

The following is an example for retrieving user defined flows. ${\tt JSON}$

Request header

TABLE 13 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

Create User Defined Flow

This topic covers the process of creating a custom open flow, by providing the match criteria and mitigation action.

Resource URL

<Base URI>/collector/customFlows

The user will be able to provide the flow priority above or below the learned and programmed flows.

To access custom open flows in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ customFlows
- 2. Define the overall traffic user parameters.
- 3. Set the HTTPS request method to POST.

Create User Defined Flow Parameters

This topic covers parameters for creating user defined flows for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Content-Type	JSON format: Application/json
	XML format: Application/xml
Operation	POST

NOTE

The POST operation is supported.

Create User Defined Flow Examples

This topic covers the fetch request for creating user defined flows for the Brocade Flow Optimizer (BFO) server.

The create user defined flows fetch request examples for BFO POST operation for flows include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/customFlows

Example of Headers Sent to BFO

The following is an example of creating user defined flows. $\ensuremath{\mathtt{JSON}}$

Request header

TABLE 14 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

Delete User Defined Flow

This topic covers the process of deleting a user defined flow, by providing the Flow ID.

Resource URL

<Base URI>/collector/customFlows/<Flow ID>

To access custom open flows in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ customFlows/<Flow ID>
- 2. Define the overall traffic user parameters.
- 3. Set the HTTPS request method to DELETE.

Delete User Defined Flow Parameters

This topic covers parameters for deleting user defined flows for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Content-Type	JSON format: Application/json XML format: Application/xml
Operation	DELETE

NOTE

The DELETE operation is supported.

Delete User Defined Flow Examples

This topic covers the fetch request for deleting user defined flows for the Brocade Flow Optimizer (BFO) server.

The delete user defined flows fetch request examples for BFO DELETE operation for flows include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/customFlows/<Flow ID>

The following is an example of deleting user defined flows. $\ensuremath{\mathtt{JSON}}$

Request header

Authorization - Administrator_1426270596791 Content-Type - Application/json Content-Type: Application/json

TABLE 15 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

Profiles

Profiles Overview	53
Create New Custom Profile	53
Edit Custom Profile	58
Delete Custom Profile	61
Get List of Profiles	63
Bulk Enabling of Profiles	66
Bulk Disabling of Profiles	68
Bulk Deletion of Profiles	70
Moving Profiles to the Top Priority	72
Moving Profiles to the Bottom Priority	74
Moving Profiles Up to the Next Priority Level	76
Moving Profiles Down to a Lower Priority Level	78

Profiles Overview

Management of profiles involve URIs to add, edit, and delete profiles; change the priority of profiles; and enable or disable a profile.

Profiles REST URIs provides some of the features listed below.

- · Add a new profile.
- · Edit a profile.
- · Enable a profile.
- · Disable a profile.
- · Change the priority of a profile.
- · Delete a profile.

Create New Custom Profile

This topic covers the process of creating a new custom profile in the Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/profile

To create a new custom profile in the BFO, complete the following steps.

- 1. Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/profile
- 2. Define the overall traffic user parameters.
- 3. Set the HTTPS request method to PUT.

Create New Custom Profile Parameters

This topic covers parameters for creating new custom profiles for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	POST

NOTE

The POST operation is supported.

Create New Custom Profile Examples

This topic covers the fetch request for creating new custom profiles for the Brocade Flow Optimizer (BFO).

Create new custom profile fetch request examples for BFO POST operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/profile

The following is an example of creating a new custom profile. $_{\ensuremath{\mathtt{JSON}}}$

Request header

```
Authorization - Administrator_1426270596791
Accept - Application/json
Content-Type:application/json
```

Request Body

Support mitigation action for the profile are NONE / DROP / REDIRECT / METER / REAMRK / MIRROR.

NONE Example

```
"name":"Custom Profile",
"description":"CustomProfile",
"type":1,
"enabled":1,
"priority":10,
"last_modified_by":"Administrator",
"id":\overline{1}01,
"observation interval_ms":34000,
"threshold":34,
"action":"NONE",
"dscp_band_enabled":false,
"network_attributes":{
     "network_attribute":[
               "name":"SRC_MAC",
"value":"ae:de:de:de:ed"
          },
               "name":"DEST_MAC",
"value":"ae:de:de:de:ed"
               "name":"IN_VLAN",
"value":"32"
               "name": "VLAN PRIORITY",
               "value":"4"
               "name":"V4_SRC_ADDR",
"value":"20.20.20.0/24"
               "name":"V4 DEST ADDR",
"value":"30.30.30.0/24"
               "name":"L3_PROTOCOL",
"value":"TCP"
               "name":"DSCP",
"value":"2"
               "name":"IP_FRAGMENT",
"value":"Yes"
               "name":"TCP_SRC_PORT",
"value":"44"
               "name":"TCP_DEST_PORT",
"value":"45"
     ]
```

```
REDIRECT Example
     "name":"Custom Profile2",
"description":" Custom Profile2",
      "type":1,
"enabled":1,
      "priority":12,
"last_modified_by":"Administrator",
     "last_modified by : Administration observation interval_ms":3000, "threshold":34, "action":"REDIRECT", "network_attributes":{
            "network_attribute":[
                 {
                      "name":"IN_VLAN",
"value":"23"
                 },
{
                      "name":"VLAN_PRIORITY",
"value":"2"
                      "name":"V4 SRC_ADDR",
"value":"22.22.33.45/24"
                      "name":"V4 DEST ADDR",
"value":"22.22.33.45/24"
                 }
           ]
     },
"redirect_nodes":{
    "redirect_node":[
                 {
                      "id":"10.24.63.241",
"ports":"49",
"portsJson":[
                                 "id":"openflow:10195223950917632:49",
"port-number":49,
"name":"eth2/1"
                      ]
                }
          ]
     }
METER Action
     "name":"Custom Profile3",
"description":"Custom Profile3",
"type":1,
     "enabled":1,
"priority":12,
"last modified_by":"Administrator",
"id":103,
     "observation interval_ms":3000, "threshold":34, "action":"METER",
     "dscp_band_enabled":true,
"network_attributes":{
            "network_attribute":[
                      "name":"IN_VLAN",
"value":"23"
                      "name":"VLAN_PRIORITY",
"value":"2"
                      "name":"V4 SRC_ADDR",
"value":"22.22.33.45/24"
```

```
},
                          "name":"V4 DEST ADDR",
"value":"22.22.33.45/24"
             ]
     },
"rate_limit":"33",
"dscp_rate_limit":"33",
"dscp_prec_level":"33",
"redirect_nodes":{
    "redirect_node":[
                          "id":"10.24.63.241",
"ports":"49",
"portsJson":[
                                 {
                                        "id": "openflow: 10195223950917632: 49",
                                       "port-number":49,
"name":"eth2/1"
                         ]
                  }
          ]
      }
MIRROR Example
      "name":"Custom Profile4",
"description":"Custom Profile4",
"type":1,
"enabled":1,
      enapled":1,
"priority":12,
"last_modified_by":"Administrator",
"id":103,
      "id":103,
"observation interval_ms":3000,
"threshold":34,
"action":"MIRROR",
"dscp_band_enabled":true,
"network_attributes":{
    "network_attribute":[
                           "name":"IN_VLAN",
"value":"23"
                          "name":"VLAN_PRIORITY",
"value":"2"
                           "name":"V4_SRC_ADDR",
"value":"22.22.33.45/24"
                          "name":"V4 DEST ADDR",
"value":"22.22.33.45/24"
                   }
             ]
      },
"redirect_nodes":{
    "redirect_node":[
                          "id":"10.24.63.241",
"ports":"50,51",
"portsJson":[
                                 {
                                       "id":"openflow:10195223950917632:50",
"port-number":50,
"name":"eth2/2"
                                       "id":"openflow:10195223950917632:51",
"port-number":51,
"name":"eth2/3"
                          ]
```

```
}
```

XML

Request Header

```
Authorization - Administrator_1426270596791    Content-Type - Application/xm\overline{l}
Accept - Application/xml
Request Body
<?xml version="1.0" encoding="UTF-8" ?>
cprofile>
    <name>Custom Profile1</name>
    <type>1</type>
    <enabled>1</enabled>
    <priority>8</priority>
    <last modified by>Administrator</last modified by>
    <observation interval ms>15000</observation_interval_ms>
<threshold>5000</threshold>
    <action>NONE</action>
    <network attributes>
         <net\overline{w}ork attribute>
              <name>IN VLAN</name>
              <value>20</value>
         </network attribute>
     </network_attributes>
</profile>
```

TABLE 16 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful update, a new custom profile is created in the BFO.

Edit Custom Profile

This topic covers the process of editing a custom profile in the Brocade Flow Optimizer (BFO).

Resource URL <Base URI>/collector/profile?profileName=<Profile Name>

To edit custom profiles in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ profile?profileName=<Profile Name>
- 2. Define the overall traffic user parameters.
- 3. Set the HTTPS request method to PUT.

Edit Profile Parameters

This topic covers parameters for editing custom profiles for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	PUT

NOTE

The PUT operation is supported.

Edit Custom Profile Examples

This topic covers the fetch request for editing custom profiles for the Brocade Flow Optimizer (BFO).

Edit custom profile fetch request examples for BFO PUT operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/profile

The following is an example of editing a custom profile. ${\tt JSON}$

```
Request header
```

```
Authorization - Administrator_1426270596791
Accept - Application/json
Content-Type: application/json
Request Body
Support mitigation action for the profile are NONE / DROP / REDIRECT / METER / REAMRK / MIRROR.
NONE Example
       "name": "Custom",
"description": "Custom Profileupdated",
       "type": 1,
"enabled": 1,
"priority": 12,
"last_modified_by": "Administrator",
       "id": 103,
      "id": 103,
"observation_interval_ms": 3000,
"threshold": 34,
"action": "MIRROR",
"dscp_band_enabled": true,
"network_attributes": {
"network_attribute": [
              "network_attribute": [
                     {
                             "name": "IN_VLAN",
"value": "23"
                      },
                             "name": "VLAN_PRIORITY",
"value": "2"
                      },
                             "name": "V4_SRC_ADDR",
"value": "22.22.33.45/24"
                     },
                             "name": "V4_DEST_ADDR",
"value": "22.22.33.45/24"
                     }
              1
       },
"redirect_nodes": {
    "redirect_node": [
                     {
                             "id": "10.24.63.241",
"ports": "50,51",
                             "portsJson": [
                                           "id": "openflow:10195223950917632:50",
"port-number": 50,
"name": "eth2/2"
                                           "id": "openflow:10195223950917632:51",
"port-number": 51,
"name": "eth2/3"
                           ]
                    }
           ]
      }
```

} NOTE

For action [REDIRECT, METER, MIRROR] the payload is same as in add operation.

XML

Request Header

Authorization - Administrator 1426270596791 Content-Type - Application/xm \overline{l} Accept - Application/xml

TABLE 17 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful update, the existing custom profile is update in the BFO.

Delete Custom Profile

This topic covers the process of deleting a custom profile in the Brocade Flow Optimizer (BFO).

Resource URL
<pre><base uri=""/>/collector/profile?profileName=<profile name=""></profile></pre>

To delete custom profiles in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ profile?profileName=<Profile Name>
- 2. Define the overall traffic user parameters.
- 3. Set the HTTPS request method to DELETE.

Delete Custom Profile Parameters

This topic covers parameters for deleting custom profiles for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	DELETE

NOTE

The DELETE operation is supported.

Delete Custom Profile Examples

This topic covers the fetch request for deleting custom profiles for the Brocade Flow Optimizer (BFO).

Delete custom profile fetch request examples for BFO DELETE operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/profile?profileName=<Profile Name>

Example of Headers Sent to BFO

The following is an example of deleting a custom profile. JSON

Request header

```
Authorization - Administrator_1426270596791
Accept - Application/json
Content-Type: application/json
```

XML

Request Header

```
Authorization - Administrator_1426270596791
Content-Type - Application/xml
Accept - Application/xml
```

TABLE 18 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful delete, existing custom profile will be deleted in the BFO.

Get List of Profiles

This topic covers how to get a list of profiles in Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/profiles

To get a list of profiles in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ profiles
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to GET.

Get List of Profiles Parameters

This topic covers parameters for getting a list of profiles for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	GET

NOTE

The GET operation is supported.

Get List of Profiles Examples

This topic covers the fetch request for getting a list of profiles for the Brocade Flow Optimizer (BFO).

Get list of profiles fetch request examples for BFO GET operation include:

- · BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/profiles

The following is an example for getting a list of profiles. $\ensuremath{\mathtt{JSON}}$

Request header

```
Authorization - Administrator 1426270596791
Accept - Application/json
Response Body
      "profile": [
             {
                   "id": 1,
"name": "NTP Reflection",
"description": "This profile is used to monitor and detect
unsolicited responses fromNTP servers. The NTP servers
                   responds to get monlist requests from a source that typically cannot be traced. The traffic is amplified and
                   results in a huge amount of monlist query responses that
                   consume the target's network resources and disrupt the network.",
                    "observation_interval_ms": 30000,
                   "threshold": 100000,
"reduced_threshold": 90000,
"action": "NONE",
                   "last_modified_time": 1439360462491,
"last_modified_by": "Administrator",
                   "enabled": 1,
"type": 0,
"priority": 3,
                   "dscp_band_enabled": false,
"flow_timeout": 0,
                    "network attributes":
                          "network attribute": [
                            "name": "L3_PROTOCOL",
"value": "UDP"
                           "name": "UDP_SRC_PORT",
"value": "123"
              ]
       }
 },
       "id": 2,
"name": "DNS_Reflection",
"description": "This profile is used to monitor and detect
        unsolicited DNS query responses coming from third party systems (usually name servers). The traffic is amplified and results
       in a huge amount of DNS query responses that consume the target's network resources and disrupt the network.", "observation_interval_ms": 15000, "threshold": 10000,
        "reduced_threshold": 9000,
"action": "NONE",
        "last_modified_time": 1439360370207,
"last_modified_by": "Administrator",
        "enabled": 1,
        "type": 0,
"priority": 4,
        "dscp_band_enabled": false,
        "flow_timeout": 0,
        "network attributes":
               "net\overline{w}ork attribute": [
                     {
                            "name": "L3_PROTOCOL",
"value": "UDP_TCP"
                     },
                     {
                           "name": "UDP_SRC_PORT",
"value": "53"
                     },
```

```
"name": "TCP_SRC_PORT",
"value": "53"
               }
          ]
     }
}
Request Header
Authorization - Guest 1426270596791
Accept - Application/xml
Request Body
<?xml version="1.0" encoding="UTF-8" ?>
    cprofiles>
         file>
              <id>1</id>
              <name>NTP Reflection</name>

<description>profile description.</description>
<observation interval ms>30000</observation interval ms>
              <threshold>100000</threshold>
              <reduced threshold>90000.0</reduced threshold>
              <action>\overline{N}ONE</action>
              <last_modified_time>1439360462491</last_modified_time>
<last_modified_by>Administrator</last_modified_by>
<enabled>1</enabled>
              <type>0</type>
              <priority>3</priority>
<dscp_band_enabled>false</dscp_band_enabled>
<flow_timeout>0</flow_timeout>
              <name>L3_PROTOCOL</name>
<value>UDP</value>
                   </network attribute>
                   <network attribute>
                        <name>UDP SRC PORT</name>
<value>123</value>
                   </network_attribute>
              </network_attributes>
         </profile>
         cprofile>
              <id>2</id>
              <name>DNS Reflection</name>
              <description> profile description.</description>
              <observation interval ms>15000</observation interval ms>
              <threshold>10000</threshold>
              <reduced threshold>9000.0</reduced threshold>
              <action>\overline{N}ONE</action>
              <last modified time>1439360370207/last modified time>
<last modified by>Administrator/last modified by>
              <enabled>1</enabled>
              <type>0</type>
              <priority>4</priority>
              <dscp band enabled>false</dscp_band_enabled>
              <flow_timeout>0</flow_timeout>
<network attributes>
                   </network_attribute>
                   <network_attribute>
     <name>TCP_SRC_PORT</name>
     <value>53/value>
                   </network_attribute>
              </network_attributes>
         </profile>
         cprofile>
              <id>6</id>
```

XMT.

```
<name>Quote of the day</name>
              <description>Quote of the day</description>
<observation_interval_ms>15000</observation_interval_ms>
              <threshold>5\overline{0}00</threshold>
              <reduced threshold>4500.0</reduced threshold>
              <action>\overline{\text{N}}ONE</action>
              <last modified time>1439359968047/last modified time>
              <last modified by>Administrator</last modified by>
              <enabled>1</enabled>
              <type>0</type>
              <priority>7</priority>
              <dscp_band_enabled>false</dscp_band_enabled>
              <flow timeout>0</flow timeout>
              <network attributes>
                   <net\overline{w}ork attribute>
                        <name>L3 PROTOCOL</name>
                        <value>UDP TCP</value>
                   </network attribute>
                   <network attribute>
                        <name>UDP_SRC_PORT</name>
<value>17</value>
                   </network attribute>
                   <network \overline{a}ttribute>
                        <name>TCP SRC PORT</name>
<value>17</value>
                   </network attribute>
              </network attributes>
         </profile>
</profiles>
```

TABLE 19 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful request, a list of profiles details will be retrieved from the BFO.

Bulk Enabling of Profiles

This topic covers the process of bulk enabling of profiles in the Brocade Flow Optimizer (BFO).

```
Resource URL

<Base URI>/collector/profiles
```

To bulk enable profiles in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ profiles
- 2. Define the overall traffic user parameters.
- 3. Set the HTTPS request method to PUT.

Bulk Enabling of Profiles Parameters

This topic covers parameters for bulk enabling profiles for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	PUT

NOTE

The PUT operation is supported.

Bulk Enabling of Profiles Examples

This topic covers the fetch request for bulk enabling of profiles for the Brocade Flow Optimizer (BFO).

Bulk enabling of profiles fetch request examples for BFO PUT operation includes:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/profiles

The following is an example of bulk enabling of profiles. JSON

Request header

```
Authorization - Administrator_1426270596791

Content-Type - Application/json

Accept - application/json

Request Body

{"action": "enable", "name": ["NTP_Reflection", "DNS_Reflection", "ICMP_Flood"]}
```

XML

Request Header

TABLE 20 Status Code

</profiles>

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful update, the profiles status will be enabled in the BFO.

Bulk Disabling of Profiles

This topic covers the process of bulk disabling of profiles in the Brocade Flow Optimizer (BFO).

Resource URL <Base URI>/collector/profiles

To bulk disable profiles in the BFO, complete the following steps.

- 1. Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/profiles
- 2. Define the overall traffic user parameters.
- 3. Set the HTTPS request method to PUT.

Bulk Disabling of Profiles Parameters

This topic covers parameters for bulk disabling of profiles for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	PUT

NOTE

The PUT operation is supported.

Bulk Disabling of Profiles Examples

This topic covers the request headers sent for bulk disabling of profiles to the Brocade Flow Optimizer (BFO).

Bulk disabling of profiles fetch request examples for BFO PUT operation includes:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/profiles

The following is an example of bulk disabling of profiles. $_{\ensuremath{\mathtt{JSON}}}$

Request header

```
Authorization - Administrator_1426270596791

Content-Type - Application/json

Accept - application/json

Request Body

{"action": "disable", "name": ["NTP_Reflection", "DNS_Reflection", "ICMP_Flood"]}
```

XML

Request Header

TABLE 21 Status Code

</profiles>

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful update, the profiles status will be disabled in the BFO.

Bulk Deletion of Profiles

This topic covers the process of bulk deletion of profiles in the Brocade Flow Optimizer (BFO).

Resource URL <Base URI>/collector/profiles

To bulk delete profiles in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ profiles
- 2. Define the overall traffic user parameters.
- 3. Set the HTTPS request method to PUT.

Bulk Deletion of Profiles Parameters

This topic covers parameters for bulk deletion of profiles for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	PUT

NOTE

The PUT operation is supported.

Bulk Deletion of Profiles Examples

This topic covers the request headers sent for bulk deletion of profiles to the Brocade Flow Optimizer (BFO).

Bulk deletion of profiles fetch request examples for BFO PUT operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/profiles

The following is an example of bulk deletion of profiles. JSON

Request header

```
Authorization - Administrator_1426270596791

Content-Type - Application/json

Accept - application/json

Request Body

{"action": "delete", "name": ["NTP_Reflection",

"DNS_Reflection", "ICMP_Flood"]}
```

XML

Request Header

<name>ICM \overline{P} Flood</name>

TABLE 22 Status Code

</profiles>

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful update, the profiles status will be deleted in the BFO.

Moving Profiles to the Top Priority

This topic covers how to move profiles to the top priority in Brocade Flow Optimizer (BFO).

Resource URL <Base URI>/collector/profiles

To move profiles to the top priority in the BFO, complete the following steps.

- 1. Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/profiles
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to PUT.

Moving Profiles to the Top Priority Parameters

This topic covers parameters for moving profiles to the top priority for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data. JSON format: Application/json XML format: Application/xml
Operation	PUT

NOTE

The PUT operation is supported.

Moving Profiles to the Top Priority Examples

This topic covers the fetch request for moving profiles to the top priority for the Brocade Flow Optimizer (BFO).

Moving profiles to the top priority fetch request examples for BFO PUT operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/profiles

The following is an example for moving profiles to the top priority.

JSON

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json
Accept - Application/json

Request Body
{"action": "top", "name": ["NTP_Reflection", "DNS_Reflection",
"ICMP_Flood"]}
```

XML

Request Header

TABLE 23 Status Code

</profiles>

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful update, the selected profiles will be moved to top priority in the BFO.

Moving Profiles to the Bottom Priority

This topic covers how to move profiles to the bottom priority in Brocade Flow Optimizer (BFO).

Resource URL <Base URI>/collector/profiles

To move profiles to the bottom priority in the BFO, complete the following steps.

- 1. Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/profiles
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to PUT.

Moving Profiles to the Bottom Priority Parameters

This topic covers parameters for moving profiles to the bottom priority for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	PUT

NOTE

The PUT operation is supported.

Moving Profiles to the Bottom Priority Examples

This topic covers the fetch request for moving profiles to the bottom priority for the Brocade Flow Optimizer (BFO).

Moving profiles to the bottom priority fetch request examples for BFO PUT operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/profiles

The following is an example for moving profiles to the bottom priority.

JSON

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json
Accept - Application/json

Request Body
{"action": "bottom", "name": ["NTP_Reflection", "DNS_Reflection",
"ICMP_Flood"]}
```

XML

Request Header

 $\verb|<name>ICMP_Flood</name>|$

TABLE 24 Status Code

</profiles>

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful update, the selected profiles will be moved to bottom priority in the BFO.

Moving Profiles Up to the Next Priority Level

This topic covers how to move profiles above their current priority level in Brocade Flow Optimizer (BFO).

Resource URL <Base URI>/collector/profiles

To move the profiles priority up (to the next level above the profile's present priority level) in the BFO, complete the following steps.

- 1. Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/profiles
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to PUT.

Moving Profiles Up to the Next Priority Level Parameters

This topic covers parameters for moving profiles above their current priority level in the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data. JSON format: Application/json XML format: Application/xml
Operation	PUT

NOTE

The PUT operation is supported.

Moving Profiles Up to the Next Priority Level Examples

This topic covers the fetch request for moving profiles above their current priority level for the Brocade Flow Optimizer (BFO).

Moving profiles up to the next priority level fetch request examples for BFO PUT operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/profiles

The following is an example for moving profiles up to the next priority level.

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json
Accept - Application/json

Request Body
{"action": "up", "name": ["NTP_Reflection", "DNS_Reflection",
"ICMP_Flood"]}
```

XML

Request Header

TABLE 25 Status Code

</profiles>

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful update, the selected profiles will be moved one priority above their current priority in the BFO.

Moving Profiles Down to a Lower Priority Level

This topic covers how to move profiles below their current priority level in Brocade Flow Optimizer (BFO).

Resource URL <Base URI>/collector/profiles

To move the profiles priority down (to a lower level than the profile's present priority level) in the BFO, complete the following steps.

- 1. Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/profiles
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to PUT.

Moving Profiles Down to a Lower Priority Level Parameters

This topic covers parameters for moving profiles below their current priority level in the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	PUT

NOTE

The PUT operation is supported.

Moving Profiles Down to a Lower Priority Level Examples

This topic covers the fetch request for moving profiles below their current priority level for the Brocade Flow Optimizer (BFO).

Moving profiles down to a lower priority level fetch request examples for BFO PUT operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/profiles

80

Example of Headers Sent to BFO

The following is an example for moving profiles down to a previous priority level. JSON

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json
Accept - Application/json
Request Body
{"action": "down", "name": ["NTP_Reflection", "DNS_Reflection", "ICMP_Flood"]}
```

XML

Request Header

```
Authorization - Administrator 1426270596791 Content-Type - Application/xml Accept - Application/xml
Request Body
<?xml version="1.0" encoding="UTF-8" ?>
files>
      <action>down</action>
      <name>NTP_Reflection</name>
<name>DNS_Reflection</name>
      <name>ICM\overline{P} Flood</name>
</profiles>
```

TABLE 26 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful update, the selected profiles will be moved one priority below their current priority in the BFO.

Settings

Settings Overview	81
Controller Settings	81
Add Controller Settings	83
Edit Controller Settings	85
Email Notification Settings	87
Add Email Settings	91
Update Email Settings	92
Retrieve sFlow Settings, SNMP and sFlow Registration	95
Add sFlow Settings	97
Update Existing sFlow Settings	99
Retrieve SNMP Profiles	101
Create SNMP Profile	103
Update Existing SNMP Profile	105
Delete Existing SNMP Profile	106

Settings Overview

Settings in the Brocade Flow Optimizer (BFO) involve URIs for setting controller, email notification, sFlow, SNMP profile management, and device management.

Settings REST URIs provides some of the features listed below.

- · Set the controller.
- · Set email notification.
- · Set sFlow settings.
- · Set SNMP profile management.
- · Set device management.

Controller Settings

This topic covers controller settings in Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/controller

The URIs return the controller information, which operation any user can perform. Password information is only returned if the user performing the operation has Administrator privileges (access_privilege=1). The connection_status specifies if controller credentials are valid, hence allowing the establishment of a connection to the controller. If no controller is present, then an empty controller object is returned.

To access controller settings in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ controller
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to GET.

Controller Settings Parameters

This topic covers parameters for controller settings for the Brocade Flow Optimizer (BFO).

Parameter Value
Authorized token.
The content type of the returned data.
JSON format: Application/json
XML format: Application/xml
GET

NOTE

The GET operation is supported.

Controller Settings Examples

This topic covers the fetch request for getting controller settings for the Brocade Flow Optimizer (BFO).

Controller settings fetch request examples for BFO GET operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/controller

The following is an example for getting controller settings. $_{\ensuremath{\mathtt{JSON}}}$

Request header

```
Authorization - Administrator_1426270596791
Accept - Application/json

Response Body
{
    "controller": {
      "url": "https://10.24.41.109:8181",
      "username": "admin",
      "password": "admin",
      "connection_status": 1
    }
}
```

<connection status>1</connection status>

XML

Request Header

```
Authorization - Guest_1426270596791
Accept - Application/xml

Request Body

<?xml version="1.0" encoding="UTF-8" standalone="yes" ?>
<controller>
<url>https://10.24.49.138:8181</url>
<username>admin</username>
<password>admin</password>
```

TABLE 27 Status Code

</controller>

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful request, controller details will be retrieved from the BFO.

Add Controller Settings

This topic covers adding controller settings in Brocade Flow Optimizer (BFO).

Resource URL <Base URI>/collector/controller

The URIs return the controller information, which operation any user can perform. Password information is only returned if the user performing the operation has Administrator privileges

(access_privilege=1). The connection_status specifies if controller credentials are valid, hence allowing the establishment of a connection to the controller. If no controller is present, then an empty controller object is returned.

To add controller settings in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ controller
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to GET.

Add Controller Settings Parameters

This topic covers parameters for adding controller settings for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	POST
	. 55.

NOTE

The POST operation is supported.

Add Controller Settings Examples

This topic covers the fetch request for adding controller settings for the Brocade Flow Optimizer (BFO).

Controller settings fetch request examples for BFO GET operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/controller

The following is an example for adding controller settings. $_{\ensuremath{\mathtt{JSON}}}$

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json

Response Body
{
    "url": "https://10.24.49.138:8181",
    "username": "admin",
    "password": "admin",
    "connection_status": 1
```

XML

Request Header

```
Authorization - Guest 1426270596791
Content-Type - Application/xml

Request Body

<?xml version="1.0" encoding="UTF-8" standalone="yes" ?>
<controller>
<url>https://10.24.49.138:8181</url>
<url>https://10.24.49.138:8181</url>
<url>https://acadmin</username>
<password>admin</password>
<connection status>1</password>
<connection status>
```

TABLE 28 Status Code

</controller>

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful request, controller settings will be added to the BFO.

Edit Controller Settings

This topic covers editing controller settings in Brocade Flow Optimizer (BFO).

Resource URL <Base URI>/collector/controller

Users with Administrator privileges (access_privilege=1) may update the controller information, including the URL, username, and password.

To edit controller settings in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ controller
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to PUT.

Edit Controller Settings Parameters

This topic covers parameters for editing controller settings for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data. JSON format: Application/json XML format: Application/xml
Operation	PUT

NOTE

The PUT operation is supported.

Edit Controller Settings Examples

This topic covers the fetch request for editing controller settings for the Brocade Flow Optimizer (BFO).

Controller settings fetch request examples for BFO PUT operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/controller

The following is an example for editing controller settings. ${\tt JSON}$

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json

Response Body
{
    "url": "https://10.24.41.110:8181",
    "username": "admin",
    "password": "admin",
    "connection_status": 1
```

XML

Request Header

```
Authorization - Guest_1426270596791
Content-Type - Application/xml
```

Response Body

```
<?xml version="1.0" encoding="UTF-8" standalone="yes" ?>
<controller>
<url>https://10.24.41.109:8181</url>
<url>
<u
```

TABLE 29 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful request, existing controller will be updated in the BFO.

Email Notification Settings

This topic covers email notification settings in Brocade Flow Optimizer (BFO).

Resource URL <Base URI>/collector/email

To access email notification settings in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ email
- 2. Define the test email settings to test the email configuration, before adding email notification settings Brocade Flow Optimizer.
- 3. Define the new user parameters.
- 4. Set the HTTPS request method to POST.

Email Test Settings

This topic covers email test settings in Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/email

To test email notification settings in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ email
- Define the test email settings to test the email configuration, before adding email notification settings Brocade Flow Optimizer.
- 3. Define the new user parameters.
- 4. Set the HTTPS request method to POST.

Email Notification Settings Parameters

This topic covers parameters for email notification settings for the Brocade Flow Optimizer (BFO).

Authorized token.
The content type of the returned data.
JSON format: Application/json
XML format: Application/xml
POST

NOTE

The POST operation is supported.

Email Notification Settings Examples

This topic covers the fetch request for email notification settings for the Brocade Flow Optimizer (BFO).

Email notification settings fetch request examples for BFO GET operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/email

The following is an example for email notification settings. JSON

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json

Response Body

{
    "enabled": "true",
    "id": "",
    "password": "",
    "server": "smtp.brocade.com",
    "port": "25",
    "replyAddress": "vnepolea@brocade.com",
    "emailAddresses": "vnepolea@brocade.com",
    "testRecipients": "vnepolea@brocade.com",
    "testEmail": "true"
}
```

XML

Request Header

TABLE 30 Status Code

</email>

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful execution, a test mail will be send to the configured email address.

Add Email Settings

This topic covers adding the email configuration in Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/email

To add email settings in the BFO, complete the following steps.

- 1. Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/email
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to POST.

Add Email Settings Parameters

This topic covers parameters for adding email settings for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	POST

NOTE

The POST operation is supported.

Add Email Settings Examples

This topic covers the fetch request for adding email settings for the Brocade Flow Optimizer (BFO).

Email settings fetch request examples for BFO GET operation include:

- · BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/email

The following is an example for adding email settings.

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json

Response Body

{
    "enabled": "true",
    "id": "",
    "password": "",
    "server": "smtp.brocade.com",
    "port": "25",
    "replyAddress": "vnepolea@brocade.com",
    "emailAddresses": "vnepolea@brocade.com"
}
```

XML

Request Header

```
Authorization - Administrator 1426270596791

Content-Type - Application/xml

Response Body

<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<email>
```

TABLE 31 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful request, email configuration will be added to the BFO.

Update Email Settings

This topic covers updating the email configuration in Brocade Flow Optimizer (BFO).

Resource URL <Base URI>/collector/email

To update email settings in the BFO, complete the following steps.

- 1. Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/email
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to PUT.

Update Email Settings Parameters

This topic covers parameters for updating email settings for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	PUT

NOTE

The PUT operation is supported.

Update Email Settings Examples

This topic covers the fetch request for updating email settings for the Brocade Flow Optimizer (BFO).

Email settings fetch request examples for BFO PUT operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/email

The following is an example for updating email settings. ${\tt JSON}$

Request header

```
Authorization - Administrator 1426270596791
Content-Type - Application/json

Request Body

{
    "enabled": "true",
    "id": "",
    "password": "",
    "server": "smtp.brocade.com",
    "port": "25",
    "replyAddress": "vnepolea@brocade.com",
    "emailAddresses": "vnepolea@brocade.com"
}
```

XML

Request Header

```
Authorization - Administrator_1426270596791    Content-Type - Application/xm\overline{\text{I}}
```

Response Body

TABLE 32 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful update, existing email settings will be updated in the BFO.

Retrieve sFlow Settings, SNMP and sFlow Registration

This topic covers retrieving the sFlow settings for SNMP and sFlow registration in the Brocade Flow Optimizer (BFO).

Resource URL <Base URI>/collector/sFlowSettings

To retrieve sFlow settings in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ sFlowSettings
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to GET.

Retrieve sFlow Settings, SNMP and sFlow Registration Parameters

This topic covers parameters to retrieve sFlow settings for SNMP and sFlow registration for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	GET

NOTE

The GET operation is supported.

Retrieve sFlow Settings, SNMP and sFlow Registration Examples

This topic covers the fetch request to retrieve sFlow settings for SNMP and sFlow registration for the Brocade Flow Optimizer (BFO).

sFlow settings for SNMP and sFlow registration fetch request examples for BFO GET operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/sFlowSettings

Example of Headers Sent to BFO

The following is an example for retrieving sFlow settings for SNMP and sFlow registration. JSON

Request header

```
Authorization - Administrator 1426270596791
Content-Type - Application/json
Accept-Content - Application/json
Request Body
 selectedNetworkInterface:
 inBand: "99.99.99.146"
outBand: "99.99.99.146"
networkInterfaceList:
 ipaddress: [12]
0: "192.168.122.1"
1: "99.99.99.146"
    "2620:100:0:fe07:250:56ff:fe87:6109%eth0"
    "2620:100:0:fe07:55bb:c699:b1f3:bfe7%eth0"
    "2620:100:0:fe07:c892:9f5:cf2:e2a1%eth0"
    "2620:100:0:fe07:41d0:b22e:a827:a5f%eth0"
    "2620:100:0:fe07:24ed:21c9:f2c7:4037%eth0"
    "2620:100:0:fe07:a8ca:27f4:3d2f:9886%eth0"
    "2620:100:0:fe07:c4bf:e9ef:d514:b584%eth0"
8:
    "2620:100:0:fe07:7d91:fddc:22a5:9de8%eth0"
    "2620:100:0:fe07:2c4c:a239:5203:f3c8%eth0"
11: "10.24.49.146"
```

XML

Request Header

```
Authorization - Administrator 1426270596791 Content-Type - Application/xm\overline{l} Accept-Content - Application/xml
```

TABLE 33 Status Code

}

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful operation, the sFlow settings details are retrieved in the BFO.

Add sFlow Settings

This topic covers adding the sFlow settings for SNMP and sFlow registration in Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/sFlowSettings

To add sFlow settings in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ sFlowSettings
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to POST.

Add sFlow Settings Parameters

This topic covers parameters for adding sFlow settings for SNMP and sFlow registration for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	POST

NOTE

The POST operation is supported.

Add sFlow Settings Examples

This topic covers the fetch request for adding sFlow settings for SNMP and sFlow registration for the Brocade Flow Optimizer (BFO).

Adding sFlow settings for SNMP and sFlow registration fetch request examples for BFO GET operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/sFlowSettings

Example of Headers Sent to BFO

The following is an example for adding sFlow settings for SNMP and sFlow registration. ${\tt JSON}$

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json
Accept-Content - Application/json

Request Body

{
    "selectedNetworkInterface": {
        "inBand": "172.26.1.61",
        "outBand": "172.26.1.61"
}
}
```

XML

Request Header

TABLE 34 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful operation, the sFlow settings are added in the BFO.

Update Existing sFlow Settings

This topic covers updating the existing sFlow settings in Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/sFlowSettings

To update sFlow settings in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ sFlowSettings
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to PUT.

Update Existing sFlow Settings Parameters

This topic covers parameters for updating the existing sFlow settings for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	PUT

NOTE

The PUT operation is supported.

Update Existing sFlow Settings Examples

This topic covers the fetch request for updating existing sFlow settings for the Brocade Flow Optimizer (BFO).

Updating existing sFlow settings fetch request examples for BFO GET operation include:

- · BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/sFlowSettings

Example of Headers Sent to BFO

The following is an example for updating existing sFlow settings. ${\tt JSON}$

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json
Accept-Content - Application/json

Request Body
{
    "selectedNetworkInterface": {
        "inBand": "172.26.1.61",
        "outBand": "172.26.1.61"
}
```

XML

Request Header

TABLE 35 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful operation, the sFlow settings are updated in the BFO.

Retrieve SNMP Profiles

This topic covers retrieving the SNMP profiles in the Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/snmpProfiles

To retrieve SNMP profiles in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ snmpProfiles
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to GET.

Retrieve SNMP Profiles

This topic covers parameters to retrieve SNMP profiles for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value	
Authorization	Authorized token.	
Accept	The content type of the returned data.	
	JSON format: Application/json	
	XML format: Application/xml	
Operation	GET	

NOTE

The GET operation is supported.

Retrieve SNMP Profiles Examples

This topic covers the fetch request to retrieve SNMP profiles for the Brocade Flow Optimizer (BFO).

SNMP profiles fetch request examples for BFO GET operation include:

- · BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/snmpProfiles

The following is an example for retrieving SNMP profiles. JSON

```
Request header
```

XML

Request Header

]

```
Authorization - Administrator 1426270596791 Content-Type - Application/xm\overline{l} Accept-Content - Application/xml
Response Body
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<snmp_profiles>
     <snmp_profile>
          p_profile>
<name>snmpsettingv1</name>
<type>v1</type>
<rw_community_string>private
</rw_community_string>
           <order>1</order>
          <last_modified_on>Mon Aug 17 16:14:57 PDT 2015
</last_modified_on>
     </snmp_profile>
     <snmp_profile>
          < \overline{n}ame>snmpsettingv3</name>
           <type>v3</type>
           <username>md5aesuser</username>
           <auth_protocol>hmac_md5</auth_protocol>
           <auth password>md5password</auth password>
           <priv_protocol>cfb_aes_128</priv_protocol>
           <priv password>aespasswords</priv password>
           <order>2</order>
           <last_modified_on>Mon Aug 17 16:16:09 PDT 2015
           </last modified on>
</snmp_profile>
</snmp_profiles>
```

TABLE 36 Status Code

HTTPS Status Code

Description

TABLE 36 Status Code (Continued)

200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful operation, the SNMP profiles are retrieved in the BFO.

Create SNMP Profile

This topic covers creating the SNMP profile in Brocade Flow Optimizer (BFO).

Resource URL		
<pre><base uri=""/>/collector/snmpProfiles</pre>		

To create an SNMP profile in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ snmpProfiles
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to POST.

Create SNMP Profile Parameters

This topic covers parameters for creating an SNMP profile for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	POST

NOTE

The POST operation is supported.

Create SNMP Profile Examples

This topic covers the fetch request for creating an SNMP profile for the Brocade Flow Optimizer (BFO).

Creating SNMP profile fetch request examples for BFO GET operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/snmpProfiles

Example of Headers Sent to BFO

The following is an example for adding sFlow settings for SNMP and sFlow registration.

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json

Request Body
{
   "name": "snmpsettingv1_another",
   "type": "V 1",
   "rw_community_string": "something_private"
}
```

XML

Request Header

TABLE 37 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful operation, the new SNMP profile is added in the BFO.

Update Existing SNMP Profile

This topic covers updating an existing SNMP profile in Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/snmpProfiles//profile name>

To update an SNMP profile in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ snmpProfiles/profile name>
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to PUT.

Update Existing SNMP Profile Parameters

This topic covers parameters for updating an existing SNMP profile for the Brocade Flow Optimizer (BFO).

A (1 1 1 1 1
Authorized token.
The content type of the returned data.
JSON format: Application/json
XML format: Application/xml
PUT

NOTE

The PUT operation is supported.

Update Existing SNMP Profile Examples

This topic covers the fetch request for updating an existing SNMP profile for the Brocade Flow Optimizer (BFO).

Updating existing SNMP profile fetch request examples for BFO GET operation include:

- · BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/snmpProfiles/ofile name>

Example of Headers Sent to BFO

The following is an example for updating an existing SNMP profile.

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json
```

Request Body

```
{
"name": "snmpsettingv1_another",
"type": "V 1",
"rw_community_string": "new_password"
}
```

XML

Request Header

```
Authorization - Administrator_1426270596791
Content-Type - Application/xml

Request Body

<snmp profile>
```

TABLE 38 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful operation, the existing SNMP profile is updated in the BFO.

Delete Existing SNMP Profile

This topic covers the process of deleting an existing SNMP profile in the Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/snmpProfiles/profile name>

To delete an existing SNMP profile in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/ snmpProfile/profile name>
- 2. Define the overall traffic user parameters.
- 3. Set the HTTPS request method to DELETE.

Delete Existing SNMP Profile Parameters

This topic covers parameters for deleting an existing SNMP profile for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	DELETE

NOTE

The DELETE operation is supported.

Delete Existing SNMP Profile Examples

This topic covers the fetch request for deleting an existing SNMP profile for the Brocade Flow Optimizer (BFO).

Delete existing SNMP profile fetch request examples for BFO DELETE operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/snmpProfiles/<profile name>

The following is an example of deleting a custom profile. $\ensuremath{\mathtt{JSON}}$

Request header

```
Authorization - Administrator_1426270596791    Content-Type: application/json
```

XML

Request Header

Authorization - Administrator 1426270596791 Content-Type - Application/xm \overline{l}

TABLE 39 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

On successful operation, existing SNMP profile will be deleted in the BFO.

Device Management

Device Management	
Retrieve Controller and Managed Devices	109
Register Devices	112
Update Registered Managed Devices	11
De-register Managed Devices	118

Device Management

Device management in the Brocade Flow Optimizer (BFO) involves URIs for retrieving controller and managed devices, registering devices, updating registered managed devices, and de-registering managed devices.

Device management REST URIs provides some of the features listed below.

- · Retrieving controller and managed devices.
- Registering devices.
- · Updating registered managed devices.
- · De-registering managed devices.

Retrieve Controller and Managed Devices

This topic covers retrieving controller and managed devices in the Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/managedDevices

<Base URI>/collector/managedDevices?ips={value}

The list of retrieved controller and managed devices includes those devices currently managed by the application and those available in the controller. The returned object is a managed_devices object containing a list of managed_device instances.

- The managed property indicates whether the device is currently managed or not.
- The status and statusMessage relays information regarding the status of the managed device, like whether it became unreachable or was removed from the controller. Any user can perform this operation.

The API also provides the user with an optional query parameter ips. This parameter can be used to retrieve specific devices. Only devices matching the listed ips will be returned.

- In the event that the device has maxed out collector addresses (maximum of 4 collectors allowed on device), then the port list will be empty, as no more ports can be registered for sflow.
- If controller has not been configured then an appropriate error is returned. If SNMP profile has not been configured then an appropriate error is returned.

To retrieve controller and manage devices in the BFO, complete the following steps.

- 1. Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/manageDevices or https://localhost:8089/collector/manageDevices?ips={value}
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to GET.

Retrieve Controller and Managed Devices Parameters

This topic covers parameters to retrieve controller and managed devices for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	GET

NOTE

The GET operation is supported.

Retrieve Controller and Managed Devices Examples

This topic covers the fetch request to retrieve controller and managed devices for the Brocade Flow Optimizer (BFO).

Retrieving controller and managed device fetch request examples for BFO GET operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/manageDevices

https://localhost:8089/collector/manageDevices?ips=(value)

Example of Headers Sent to BFO

The following is an example for retrieving sFlow settings for SNMP and sFlow registration.

JSON

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json
Accept-Content - Application/json

Request Body

{
    "managed_device": [
        "ip_address": "10.24.63.240",
        "device_type": "MLX",
        "statusMessage": "Success",
        "managed": 0,
        "snmp_profile_name": "",
        "last_modified_on": ""
    },
    {
        "ip_address": "10.24.63.241",
        "device_type": "MLX",
        "statusMessage": "Success",
        "managed": 0,
        "statusMessage": "Success",
        "managed": 0,
        "snmp_profile_name": "",
        "last_modified_on": ""
    },
    {
        "ip_address": "10.24.50.180",
        "device_type": "MLX",
        "statusMessage": "Success",
        "managed": 0,
        "statusMessage": "Success",
        "
```

XML

Request Header

```
Authorization - Administrator 1426270596791 Content-Type - Application/xm\overline{l} Accept-Content - Application/xml
```

Response Body

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<managed_devices>
    <managed_device>
        <statusMessage>Success</statusMessage>
        <managed>0</managed>
        <snmp profile name></snmp profile name>
        <last_modified_on></last_modified_on>
    </managed device>
    <managed device>
        <ip address>10.24.63.241</ip address>
        <device type>mlx</device type>
        <status>0</status>
        <statusMessage>Success</statusMessage>
        <managed>0</managed>
    <snmp_profile_name></snmp_profile_name>
    <last_modified_on></last_modified_on>
</managed_device>
    <managed device>
        <ip address>10.24.50.180</ip address>
```

TABLE 40 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

Register Devices

This topic covers registering devices in the Brocade Flow Optimizer (BFO).

Resource URL
<pre><base uri=""/>/collector/managedDevices</pre>

To register devices in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/managedDevices
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to POST.

Register Devices Parameters

This topic covers parameters for registering devices for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	POST

NOTE

The POST operation is supported.

Register Devices Examples

This topic covers the fetch request for registering devices for the Brocade Flow Optimizer (BFO).

Registering devices fetch request examples for BFO GET operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/managedDevices

Example of Headers Sent to BFO

The following is an example for registering devices. JSON

```
Request header
```

XML

Request Header

]

```
Authorization - Administrator 1426270596791 Content-Type - Application/xm\overline{l} Accept-Content - Application/json
Request Body
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<managed devices>
      <managed device>
           <ip address>10.24.63.240</ip address>
           <device_type>mlx</device_type>
           <intrfaces>
                 <intrface>
                       <if_index>2</if_index>
<if_description>1/2</if_description>
<sflow_enabled>1</sflow_enabled>
                 </intrface >
      </managed_device>
<managed_device>
           <ip_address>10.24.63.241</ip_address>
           <device_type>mlx</device_type>
           <intrfaces>
                 <intrface>
                       <if index>2</if index>
<if_description>1/2</if_description>
<sflow_enabled>1</sflow_enabled>
                 </intrface>
           </intrfaces>
      </managed device>
</managed_devices>
```

TABLE 41 Status Code

HTTPS Status Code

Description

TABLE 41 Status Code (Continued)

200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

Update Registered Managed Devices

This topic covers updating registered managed devices in Brocade Flow Optimizer (BFO).

Resource URL
<pre><base uri=""/>/collector/managedDevices</pre>

To update registered managed devices in the BFO, complete the following steps.

- 1. Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/managedDevices
- 2. Define the new user parameters.

The PUT operation is supported.

3. Set the HTTPS request method to PUT.

Update Registered Managed Devices Parameters

This topic covers parameters for updating registered managed devices for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data. JSON format: Application/json
	XML format: Application/xml
Operation	PUT
NOTE	

Update Registered Managed Devices Examples

This topic covers the fetch request for updating registered managed devices for the Brocade Flow Optimizer (BFO).

Updating registered managed devices fetch request examples for BFO GET operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

https://localhost:8089/collector/managedDevices

Example of Headers Sent to BFO

The following is an example for updating registered managed devices. ${\tt JSON}$

Request header

XML

Request Header

```
Authorization - Administrator 1426270596791 Content-Type - Application/xm\overline{l} Accept-Content - Application/json
Request Body
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<managed devices>
     <managed device>
          <ip_address>10.24.63.240</ip_address>
<device_type>mlx</device_type>
          <intrfaces>
                <intrface>
               <intrface>
                     <if_index>2</if_index>
                     <if_description>1/2</if_description>
<sflow_enabled>1</sflow_enabled>
                </intrface>
          </intrfaces>
     </managed_device>
     <managed device>
          <ip_address>10.24.63.241</ip_address>
<device_type>mlx</device_type>
          <intrfaces>
                <intrface>
                     <if_index>2</if_index>
<if_description>1/2</if_description>
                     <sflow enabled>1</sflow_enabled>
                </intrface>
                <intrface>
                     <if index>3</if index>
<if_description>1/3</if_description>
                <sflow_enabled>1</sflow_enabled>
</intrface>
```

</intrfaces>
 </managed_device>
</managed_devices>

TABLE 42 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

De-register Managed Devices

This topic covers de-registering managed devices in Brocade Flow Optimizer (BFO).

Resource URL
<pre><base uri=""/>/collector/managedDevices/<device_ip></device_ip></pre>
<pre><base uri=""/>/collector/managedDevices/<device_ip>?deleteOnly={value}</device_ip></pre>

To de-register managed devices in the BFO, complete the following steps.

- Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/managedDevices/<device_IP> or https://localhost:8089/collector/managedDevices/<device_IP>? deleteOnly={value}
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to DELETE.

De-register Managed Devices Parameters

This topic covers parameters for de-registering managed devices for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	DELETE

NOTE

The DELETE operation is supported.

De-register Managed Devices Examples

This topic covers the fetch request for de-registering managed devices for the Brocade Flow Optimizer (BFO).

De-registering managed devices fetch request examples for BFO GET operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

```
https://localhost:8089/collector/managedDevices/<device_IP> or https://localhost:8089/collector/managedDevices/<device IP>?deleteOnly={value}
```

Example of Headers Sent to BFO

The following is an example for de-registering managed devices. Json

Request header

```
Authorization - Administrator_1426270596791
Content-Type - Application/json
Accept-Content - Application/json
```

XML

Request Header

```
Authorization - Administrator 1426270596791 Content-Type - Application/xm\overline{l} Accept-Content - Application/json
```

TABLE 43 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

De-register Managed Devices Examples

Events

•	Events Overview.	12	21
•	Retrieve Events.	12	21

Events Overview

Events in the Brocade Flow Optimizer (BFO) involve URIs for retrieving events.

Retrieve Events

This topic covers retrieving events in the Brocade Flow Optimizer (BFO).

Resource URL

<Base URI>/collector/events

<Base URI>/collector/events?timeline={}&duration={}&offset={}&limit={}

The returned object is an events object containing a list of event instances. Any user can perform this operation. The API provides a few query parameters to filter for the events. If none are specified, then the last 30 minutes of events are returned.

User can specify timeline and duration or offset and limit.

- By specifying timeline and duration, user can retrieve events for the specified duration from the specified timeline.
- By specifying the offset and limit, user can retrieve events in pages starting from a given offset and containing limit number of events per page.

Timeline takes precedence over offset.

- · If both timeline and offset are null, then timeline is considered and is set to default.
- · If both timeline and offset are specified and not null, then timeline is considered, offset is ignored.

To retrieve events in the BFO, complete the following steps.

- 1. Enter the following URI in the URL field of your REST client tool: https://localhost:8089/collector/events or https://localhost:8089/collector/events?timeline={}&duration={}&offset={}&limit={}
- 2. Define the new user parameters.
- 3. Set the HTTPS request method to GET.

Retrieve Events Parameters

This topic covers parameters to retrieve events for the Brocade Flow Optimizer (BFO).

Parameter Name	Parameter Value
Authorization	Authorized token.
Accept	The content type of the returned data.
	JSON format: Application/json
	XML format: Application/xml
Operation	GET

NOTE

The GET operation is supported.

Query Parameter Name	Value	Default Value
timeline	The time from which the duration is referenced in milliseconds.	Current time
duration	The duration from the timeline in milliseconds.	180,000 milliseconds (30 minutes)
offset	The numerical offset from 0 to get events in pages.	0
limit	The number of events per page.	1,000

Retrieve Events Examples

This topic covers the fetch request to retrieve events for the Brocade Flow Optimizer (BFO).

Retrieving events fetch request examples for BFO GET operation include:

- BFO URI
- · BFO request headers sent

Example of BFO URI

The following is an example of the BFO URI.

```
https://localhost:8089/collector/events
https://localhost:8089/collector/events?
timeline={}&duration={}&offset={}&limit={}
```

Example of Headers Sent to BFO

The following is an example for retrieving events.

Request header

Request Header

XML

```
Authorization - Administrator_1426270596791
Content-Type - Application/xml
Accept-Content - Application/json
```

Response Body

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>
<events>
    <timeline>1439873035912</timeline>
    <duration>1800000</duration>
    <event>
        <description>Profiles NTP_Reflection
        disabled Successfully</description>
        <category>AUDIT</category>
        <messageID>1007</messageID>
        <timestamp>1439872936431</timestamp>
        <severity>INFO</severity>
    </event>
    <event>
        <description>Profiles ICMP Flood
        disabled Successfully</description>
        <category>AUDIT</category>
        <messageID>1007</messageID>
        <timestamp>1439872944487</timestamp>
        <severity>INFO</severity>
    </event>
```

TABLE 44 Status Code

HTTPS Status Code	Description
200 OK	SUCCESS
400 Bad Request Error	FAILED, reason included in HTTPS error response
500 Internal Server Error	FAILED, reason included in HTTPS error response

Protocol Support

Protocol Support Default HTTPS

The Brocade Flow Optimizer (BFO) protocol support is exclusively supported for HTTPS.

NOTE

BFO works on HTTPS only. All REST HTTPS requests will be rejected.

All REST operations will be provided at the following base context path.

TABLE 45 HTTPS Protocol Support

HTTPS Default Port	HTTPS URL
8089	https:// <bfo ip="" server="">:8089</bfo>

Protocol Support Default HTTPS

ContentType Support

ContentType Support REST Requests

All REST requests that return data will support both XML and JSON formats.

NOTE

Depending on the content type requested by the user, the proper format of data will be returned.

Accept HTTPS Request Header

For GET requests, the client must specify the data format of responses. This is done by filling in the HTTPS header information. The content type for the response data is specified through the HTTPS request header named Accept as stated below.

The value for the content type is in following format:

MEDIA type/MIME subtype; Version Identifier

NOTE

refer to the Versioning section for details on the version identifier.

The user must add the header while forming the HTTPS GET request. Supported header values include the following:

TABLE 46 Accept HTTPS Request Header

Request Header Name	Request Header Value	Response Data Format
Accept	Application/xml	XML
Accept	Application/json	JSON

Conditions for Accept HTTPS request headers include the following:

- The default version value is the latest version, unless the user specifies a specific version value in the form vx, where x is the latest version for the Accept HTTPS request header name.
- The default format value is xml, unless the user specifies a format value for the Accept HTTPS request header name.

Content-type HTTPS Request Header

In the case of POST requests, in addition to specifying the format of the data of the responses via the Accept header, clients must also specify the format of the data that they are sending through the input request payload. This is done by filling in the HTTPS Content-type header.

The content type for the request data is specified through the HTTPS request header named Content-type as stated below.

TABLE 47 Content-type HTTPS Request Header

Request Header Name	Request Header Value	Request Data Format
Content-type	Application/xml	XML
Content-type	Application/json	JSON

Error Handling

	Error Handlin	1	12	0	a
•			12	-0	J

Error Handling

SdnException is the exception for all REST errors. This exception contains an integer errorCode and a string errorMessage.

The exception will be a string of the following format:

```
SdnException [errorCode=<int>, errorMsg=<string>]
```

REST operations are HTTPS requests, so the execution of an operation returns an HTTPS status code. For successful operations the status code will usually be 200 (OK) or 204 (No Content).

In the case of an error, depending on the reason for failure, any of the HTTPS status codes may be returned. But in the case of an API error, the HTTPS status code will be 500 (Internal Server Error). More details on the server error can be obtained from the SdnException embedded in the HTTPS response.

Stated below are the SdnException error codes.

TABLE 48 Error Codes

Error Code	Description
1000	Internal server error.
1001	Database exception
1002	Exception while getting Event Profile Info from database.
1003	Exception while creating Event in database.
1004	Name of profile is null or empty.
1005	Exception while getting Profiles from database.
1006	Failed to convert string to Errors object.
1008	Device SNMP communication failed, SNMP error is: {0}
2001	Invalid input parameters-granularity cannot be greater than duration.
2002	Size of utilizations in database are not equal for populating or aggregating data.
2003	User name cannot be empty. User name should not exceed 128 characters, valid characters alphanumeric, space, -, ., and ~

TABLE 48 Error Codes (Continued)

Error Code	Description
2004	Password cannot be empty, Password length should be at least 8 characters and should not exceed 75 characters.
2005	Invalid user name or password.
2006	User does not exist.
2007	Password encryption error -{0}
2008	User sessions have reached maximum limit.
2009	Invalid token.
2010	User does not have sufficient privileges.
2011	Root user account cannot be deleted.
2012	Duplicate user, the specified user already exists.
2013	Root user account cannot be updated.
2014	Invalid input parameters -start time is greater than end time.
2015	Invalid Request, Large flow ld is null or empty.
2016	Invalid Request, Pro fileld is null or empty.
2017	Traffic flow details is null.
2018	Profile details is null.
2019	Controller URL is null or empty.
2020	Controller user name is null or empty.
2021	Controller password is null or empty.
2022	Controller already exists.
2023	Controller does not exist.
2024	Controller URL is invalid -{0}
2025	Invalid SNMP profile name, it is null or empty.
2026	Invalid SNMP version.
2027	Duplicate SNMP profile, the specified SNMP profile already exists.

TABLE 48 Error Codes (Continued)

Error Code	Description
2028	Invalid auth password, it is null or empty.
2029	Invalid priv password, it is null or empty.
2030	SNMP profile {0} does not exist.
2031	SDN Controller settings must be configured to get available devices.
2032	Invalid no of SNMP profiles, two are needed for swapping.
2033	Invalid device IP, IP address is null or empty.
2034	Device {0} is already managed.
2035	The re are no SNMP profiles to manage device, please configure at least one SNMP profile.
2036	Input port list for device {0} is empty, user has to specify at least one device port.
2037	SDN Controller {0} is not reachable, please check and update SDN Controller settings.
2038	Device {0} is not managed.
2039	Device {0} cannot be managed because it is missing in the controller. Please delete device.
2040	Cannot register on device, there are already 4 collectors on device.
2041	Device{0} cannot be managed because collector is missing on device. Please delete device and add again.
2042	Collector IP is missing, please configure collector.
2043	Username cannot be empty.
2044	Password cannot be empty.
2500	DB: Failed to insert the Large flow for key {0} checksum {1}
2501	DB: Failed to update the Large flow for key {0} checksum {1}
2502	DB: Failed to move the Large flow for key {0} to completion.
2503	DB: Failed to insert the Traffic flow details for checksum {0}
2504	DB: Failed to update Time series 1 sec data for checksum {0}
2505	DB: Failed to fetch the active Large flow details.

TABLE 48 Error Codes (Continued)

Error Code	Description
2506	DB: Failed to purge entries for {0} table.
3001	The action {0} for flow {1} configuration is not supported.
4001	Could not retrieve nodes from BVC.
4002	Nodes from BVCare null or empty.
5001	Profile Name cannot exceed more than 128 characters.
5002	Invalid observation interval value. Minimum observation interval valid is 5.
5003	Invalid threshold value.
5004	Invalid profile type.
5005	Invalid profile status.
5006	Invalid username.
5007	Invalid mitigation action.
5008	Priority already set. Please use different priority.
5009	Network Attributes cannot be empty.
5010	Profile cannot have same network attribute twice.
5011	Destination MAC cannot be empty.
5012	Source MAC cannot be empty.
5013	Source VLAN cannot be empty.
5015	IPv4 source address cannot be empty.
5014	VLAN Priority cannot be empty.
5016	IPv4 destination address cannot be empty.
5017	IPv6 source address cannot be empty.
5018	IPv6 destination address cannot be empty.
5019	IP Protocol cannot be empty.
5020	DSCP cannot be empty.

TABLE 48 Error Codes (Continued)

Error Code	Description
5021	TCP source or dest port is invalid.
5022	TCP destination port cannot be empty.
5023	UDP source or dest port is invalid.
5024	UDP destination port cannot be empty.
5025	TCP Flags cannot be empty.
5026	IP Fragment cannot be empty.
5027	Invalid MAC format. Please provide the MAC address in format 11:22:33:44:55:66
5028	Invalid INVLAN string.
5029	Invalid VLANID. Valid Range: 1 to 4095.
5030	Invalid VLAN priority.
5031	Invalid VLAN priority. Valid Range: 0-7
5032	VLANID has to be selected for setting VLAN priority.
5033	Invalid IPv4 source address. Please enter valid IP address in CIDR format.
5034	Invalid IPv4 destination address. Please enter valid IP address in CIDR format.
5035	Invalid IPv6 source address. Please enter valid IP address in CIDR format.
5036	Invalid IPv6 destination address. Please enter valid IP address in CIDR format.
5037	Invalid IP Protocol. Valid values: TCP / UDP / ICMP
5038	Invalid DSCP. DSCP should be an integer value. Valid Range: 0-63
5039	IPv6 address cannot be selected when you want to set IPv4 source or destination.
5040	IPv4 address cannot be selected when you want to set IPv6 source or destination.
5041	The IP Protocol must be set to TCP when TCP Port is selected.
5042	UDP Port cannot be selected when TCP port is selected.
5043	The IP Protocol must be set to UDP when UDP Port is selected.
5044	TCP Port cannot be selected when UDP port is selected.

TABLE 48 Error Codes (Continued)

Error Code	Description
5045	The IP Protocol must be set to TCP when TCP Flag is selected.
5046	Invalid TCP flag. Valid values: URG / ACK / PSH / RST / SYN / FIN
5047	Only yes / No is allowed for IP fragment option.
5050	When redirect action selected, please provide the redirect node and port.
5051	Invalid Redirect node or port. Valid Format Node: 10.45.67.4; Port: 1, 2. Ingress port cannot be same as Mirror port.
5052	The profile name \"{0}\" from query parameter and profile name \"{1}\" from profile object does not match.
5053	Failed to search user name for given userId.
5054	Failed to insert profile {0}
5055	Failed to insert mitigation association {0} {1}
5056	Failed to insert profile attribute association {0} {1} {2}
5057	Failed to delete the profile {0}
5058	Failed to update the profile {0}
5059	Failed to delete profile mitigation association for profile {0}
5060	Failed to delete profile attribute association for profile {0}
5061	The node with IP: {0} is not discovered in BVC.
5062	Failed to create flow request. ProfileName: {0} Action: {1} FlowKey: {2}
5063	Failed to Program Flow for {0} on BVC for node: {1} for destination {2}
5064	Failed to create meter for {0} on BVC for node: {1} for VLAN: {2}
5065	Failed to Program Flow for {0} on BVC for node: {1} for VLAN: {2}
5066	Failed to delete meter for {0} on BVC for node: {1} for VLAN: {2}
5067	Failed to get configured nodes for programming flow: {0}
5068	Failed to create meter for {0} on BVC for node: {1}
5069	Failed to validate IP address {0} during the Large flow detection.

TABLE 48 Error Codes (Continued)

	Paradiation
Error Code	Description
5070	Please select NONE as an action when any of the detection only parameters are selected.
5071	Ingress port is required for METER action.
5072	Please provide valid Ingress node and port for METER action.
5073	Only one Ingress node and port are allowed for METER / MIRROR action.
5074	VLANID is mandatory network attribute for metering the traffic.
5075	Invalid Rate limit value for meter.
5076	Invalid DSCP Rate limit value for meter.
5077	DSCP Remark rate limit should be less than Drop rate limit.
5078	Invalid Profile Name. Only Alphanumeric, Space and - / . / _ / ~ are allowed.
5079	Profile with name \"{0}\" already exists.
5080	VLAN ID is mandatory network attribute when you select MIRROR as an action.
5081	There are too many wildcard attributes for the profile {0}. Maximum is 2.
5082	Action is in valid for the profile {0} with wildcard attribute. Only NONE action is supported for a profile with wildcard attribute.
5083	Maximum of 50 profiles is allowed. Please remove one or more profiles before adding new profile.
5084	Mirror action is invalid for default profiles.
5085	Ingress and Mirror port a re-required for MIRROR action.
6001	Error while initializing the PBE security key.
6002	Error while encrypting the text.
6003	Error while decrypting the text.
7001	Failed to retrieve the sFlow settings.
7002	Failed to retrieve the Network interfaces from Brocade Flow Optimizer host.
7003	Failed to inserts Flow settings.
7004	Failed to updates Flow settings.

TABLE 48 Error Codes (Continued)

Error Code	Description
7005	Invalid in-band or out-of-band address.
8001	Failed to send mail to the recipients.
8002	Invalid parameters for email configurations.

URI Return Behavior

This section explains in detail the error a user can expect when a URI fails.

Parsing of the URI follows a pattern and returns an error in the order stated below.

- First the URI is checked for correctness. If the URI is not valid (such as in the case of a
 misspelling), then the resource will not be found, and user should get an HTTPS status code of 404
 (Not Found).
- If the above PATH PARAM check succeeds, then the QUERY PARAM values (i.e. the query parameters) are checked for correctness. If the query parameters are invalid, the REST operation should fail with the HTTPS status code of 500 (Internal Server Error) and an SdnException. The value of the error code will depend on the exact error.
- If the above QUERY PARAM check succeeds, then syntactically, the URI is correct. The URI is parsed from left to right. If any resource corresponding to the PATH PARAM is not present starting from the left, then the appropriate <code>Does Not Exist</code> or <code>Not Found</code> error is reported.

For example:

```
<BASE-URI>/profiles/<profile Name>
```

In the URI above, if the resourcegroup specified by path parameter rgkey does not exist, then the user should receive an appropriate error code. If rgkey is a valid key, then the existence of fcskey is checked and so on.

- The Not Found error code is returned if you are looking for a specific object.
- In the case of a collection like fcswitches, the response will be either a populated or empty list. The return of an empty list, itself, suggests to the user that there are such instances within the requested collection.